REMOTE CONTROL MANUAL

MODELS 9420/24/50 DUAL- AND QUAD-CHANNEL DIGITAL OSCILLOSCOPES

Serial Number 2135
February 1990

<u>LeCro</u>y

Corporate Headquarters

700 Chestnut Ridge Road Chestnut Ridge, NY 10977-6499 Tel: (914) 425-2000, TWX: 710-577-2832

European Headquarters

2, chemin Pré-de-la-Fontaine P.O. Box 341 1217 Meyrin 1/Geneva, Switzerland Tel.: (022) 719 21 11, Telex: 419 058

Copyright[®] February 1990, LeCroy. All rights reserved. Information in this publication supersedes all earlier versions. Specifications subject to change.

TABLE OF CONTENTS

1	General Information	
	Initial Inspection	1
	Warranty	1
	Product Assistance	1
	Maintenance Agreements	1
	Document Discrepancies	2
	Service Procedure	2
	Return Procedure	2
2	About Remote Control	
	GPIB Implementation Standard	3
	Program Messages	3
	Commands and Queries	4
	Local and Remote State	5
	Program Message Form	5
	Command/Query Form	6
	Response Message Form	9
3	GPIB Operation	
	GPIB Structure	11
	Interface Capabilities	11
	Addressing	12
	GPIB Signals	12
	IEEE 4888.1 Standard Messages	13
	Programming GPIB Transfers	15
	Programming Service Requests	19
	Instrument Polls	21
	Driving a Hard-copy Device	25
4	RS-232-C Operation	
	Introduction	29
	RS-232-C Pin Assignments	29
	RS-232-C Configuration	30
	Commands Simulating GPIB Commands	33

5	System Commands	
	Organization	35
	Command Summary	35
	Command Execution	37
	Command Notation	37
6	Waveform Structure	
	Introduction	159
	Logical Data Blocks of a Waveform	159
	Inspect? Command	160
	Waveform? Command	162
	Waveform Command	167
	More Control of Waveform Queries	168
	High-speed Waveform Transfer	168
7	Status Registers	
	Overview of Status and Service Request Reporting	17
	Status Byte Register (STB)	173
	Standard Event Status Register (ESR)	174
	Standard Event Status Enable Register (ESE)	173
	Service Request Enable Register (SRE)	17:
	Parallel Poll Enable Register (PRE)	173
	Internal State Change Status Register (INR)	17:
	Internal State Change Enable Register (INE)	170
	Command Error Status Register (CMR)	170
	Device Dependent Error Status Register (DDR)	170
	Execution Error Status Register (EXR)	170
	User Request Status Register (URR)	17

Appendix A	
Example 1: Use of the Interactive GPIB Program 'IBIC'	179
Example 2: GPIB Program for IBM PC (High-level Function Calls)	180
Example 3: GPIB Program for IBM PC (Low-level Function Calls)	182
Appendix B	
The Waveform Template	185

	The second secon
	<u> </u>
	4

GENERAL INFORMATION

INITIAL INSPECTION

It is recommended that the shipment be thoroughly inspected immediately upon delivery to the purchaser. All material in the container should be checked against the enclosed Packing List. LeCroy cannot accept responsibility for shortages in comparison with the Packing List unless notified promptly. If the shipment is damaged in any way, please contact the Customer Service Department or local field office immediately.

WARRANTY

LeCroy warrants its oscilloscope products to operate within specifications under normal use for a period of two years from the date of shipment. Spares, replacement parts and repairs are warranted for 90 days. The instrument's firmware is thoroughly tested and thought to be functional, but is supplied "as is" with no warranty of any kind covering detailed performance. Products not manufactured by LeCroy are covered solely by the warranty of the original equipment manufacturer.

In exercising this warranty, LeCroy will repair or, at its option, replace any product returned to the Customer Service Department or an authorized service facility within the warranty period, provided that the warrantor's examination discloses that the product is defective due to workmanship or materials and that the defect has not been caused by misuse, neglect, accident or abnormal conditions or operation.

The purchaser is responsible for the transportation and insurance charges arising from the return of products to the servicing facility. LeCroy will return all in-warranty products with transportation prepaid.

This warranty is in lieu of all other warranties, expressed or implied, including but not limited to any implied warranty of merchantability, fitness, or adequacy for any particular purpose or use. LeCroy shall not be liable for any special, incidental, or consequential damages, whether in contract or otherwise.

PRODUCT ASSISTANCE

Answers to questions concerning installation, calibration, and use of LeCroy equipment are available from the Customer Service Department, 700 Chestnut Ridge Road, Chestnut Ridge, New York 10977–6499, U.S.A., tel. (914)578–6059, and 2, chemin Préde-la-Fontaine, 1217 Meyrin 1, Geneva, Switzerland, tel. (41)22/719 21 11, or your local field engineering office.

MAINTENANCE AGREEMENTS

LeCroy offers a selection of customer support services. For example, maintenance agreements provide extended warranty and allow the customer to budget maintenance costs after the initial two year warranty has expired. Other services requested by the customer such as installation, training, on–site repair, and addi-

tion of engineering improvements are made available through specific Supplemental Support Agreements.

DOCUMENTATION DISCREPANCIES

LeCroy is committed to providing state-of-the-art instrumentation and is continually refining and improving the performance of its products. While physical modifications can be implemented quite rapidly, the corrected documentation frequently requires more time to produce. Consequently, this manual may not agree in every detail with the accompanying product. There may be small discrepancies in the values of components for the purposes of pulse shape, timing, offset, etc., and, occasionally, minor logic changes. Where any such inconsistencies exist, please be assured that the unit is correct and incorporates the most up-to-date circuitry. In a similar way the firmware may undergo revision when the instrument is serviced. Should this be the case, manual updates will be made available as necessary.

SERVICE PROCEDURE

Products requiring maintenance should be returned to the Customer Service Department or authorized service facility. LeCroy will repair or replace any product under warranty at no charge. The purchaser is only responsible for the transportation charges arising from return of the goods to the service facility.

For all LeCroy products in need of repair after the warranty period, the customer must provide a Purchase Order Number before any equipment which does not operate correctly can be repaired or replaced. The customer will be billed for the parts and labor for the repair, as well as for shipping.

RETURN PROCEDURE

To determine your nearest authorized service facility, contact the Customer Service Department or your field office. All products returned for repair should be identified by the model and serial numbers and include a description of the defect or failure, name and phone number of the user, and, in the case of products returned to the factory, a Return Authorization Number (RAN). The RAN may be obtained by contacting the Customer Service Department in New York, tel. (914)578–6097, in Geneva, tel. (41)22/719 21 11, or your nearest sales office.

Return shipments should be made prepaid. LeCroy will not accept C.O.D. or Collect Return Shipments. Air-freight is generally recommended. Wherever possible, the original shipping carton should be used. If a substitute carton is used, it should be rigid and be packed such that the product is surrounded with a minimum of four inches of excelsior or similar shock-absorbing material. In addressing the shipment, it is important that the Return Authorization Number be displayed on the outside of the container to ensure its prompt routing to the proper department within LeCroy.

Two modes of operation are available in the oscilloscope. The instrument may be operated either manually, by using the front-panel controls, or remotely by means of an external controller (which is usually a computer, but may be a simple terminal). This Remote Control Manual describes how to control the oscilloscope in the remote mode. For explanations on how to manually set front-panel controls, refer to the Operator's Manual.

The oscilloscope is remotely controlled via either the GPIB (General Purpose Interface Bus) or the RS-232-C communication ports. Whenever the rear-panel GPIB address switches are set between 0 and 30, control is via GPIB; when they are at 31 or above, control is via RS-232-C. The instrument can be fully controlled in remote mode. The only actions which cannot be performed remotely are switching on the instrument or setting the remote address.

This section introduces the basic remote control concepts which are common to both RS-232-C and GPIB. It also presents a brief description of remote control messages.

Sections 3 and 4 explain how to send program messages over the GPIB or the RS-232-C interfaces, respectively. Section 5 alphabetically lists all the remote control commands. Section 6 is a detailed description and tutorial of the transfer and format of waveforms, whereas Section 7 explains the use of status bytes for error reporting. Appendix A shows some complete programming examples. Appendix B contains a printout of a waveform template.

GPIB IMPLEMENTATION STANDARD

The remote commands conform to the GPIB IEEE 488.2 standard¹. This new standard may be seen as an extension of the IEEE 488.1 standard which dealt mainly with electrical and mechanical issues. The IEEE 488.2 recommendations have also been adopted for RS-232-C communications whenever applicable.

PROGRAM MESSAGES

To remotely control the oscilloscope the controller must send program messages which conform to precise format structures. The instrument will execute all program messages which are in the correct form and ignore those where errors are detected.

^{1.} ANSI/IEEE Std. 488.2-1987, "IEEE Standard Codes, Formats, Protocols, and Common Commands", The Institute of Electrical and Electronics Engineers Inc., 345 East 47th Street, New York, NY 10017, USA.

Warning or error messages are normally not reported by the instrument, unless the controller explicitly examines the relevant status register, or if the status enable registers have been set in such a way that the controller can be interrupted when an error occurs. The status registers are explained in Section 7.

During the development of the control program it is possible to observe all remote control transactions, including error messages, on an external monitor connected to the RS-232-C port. Refer to the command "COMM_HELP" for further details.

COMMANDS AND QUERIES

Program messages consist of one or several commands or queries. A command directs the instrument to change its state, e.g. to change its time base or vertical sensitivity. A query asks the instrument about its state. Very often, the same mnemonic is used for a command and a query, the query being identified by a <?> after the last character.

For example, to change the time base to 2 msec/div, the controller should send the following command to the instrument

TIME DIV 2 MS

To ask the instrument about its time base, this query should be sent

TIME_DIV?

A query causes the instrument to send a response message. The control program should read this message with a "read" instruction to the GPIB or RS-232-C interface of the controller. The response message to the query above might be

TIME DIV 10 NS

The portion of the query preceding the question mark is repeated as part of the response message. If desired, this text may be suppressed with the command "COMM HEADER".

Depending on the state of the instrument and the computation to be done, the controller may have to wait up to several seconds for a response. Command interpretation does not have priority over other oscilloscope activities. It is therefore judicious to set the controller IO timeout conditions to 3 or more seconds. In addition, it must be remembered that an incorrect query message will not generate a response message.

LOCAL AND REMOTE STATE

As a rule, remote commands are only executed by the instrument when it is in the REMOTE state, whereas queries are always executed. A few commands which don't affect the state of the front panel are also executed in LOCAL (refer to the beginning of Section 5 for a list of these commands). When the instrument is in REMOTE, all front-panel controls are disabled, except the lefthand menu buttons, the intensity controls (which can be disabled with the command "INTENSITY") and the LOCAL button (which can be disabled by setting the instrument to LOCAL LOCKOUT). For an explanation on how to set the instrument to LOCAL, REMOTE or LOCAL LOCKOUT, refer to Section 3 for GPIB and to Section 4 for RS-232-C.

PROGRAM MESSAGE **FORM**

An instrument is remotely controlled with program messages which consist of one or several commands or queries, separated by semicolons <;> and ended by a terminator:

<command/query>;.....;<command/query> <terminator>

Upper and/or lower case characters can be used for program messages.

The instrument does not decode an incoming program message before a terminator has been received (exception: if the program message is longer than the 256 byte input buffer of the instrument, the oscilloscope starts analyzing the message when the buffer is full). The commands or queries are executed in the order in which they are transmitted.

In GPIB mode, the following are valid terminators:

<EOI>

<NL> New-line character (i.e. the ASCII new-line character, whose decimal value is 10).

New-line character with a simultaneous <EOI> <NL> <EOI> signal.

<EOI> signal together with the last character of

the program message.

Note: The <EOI> signal is a dedicated GPIB interface line which can be set with a special call to the GPIB interface driver. Refer to the GPIB interface manufacturer's manual and support pro-

The <NL> <EOI> terminator is always used in response messages sent by the instrument to the controller.

In RS-232-C, the terminator may be defined by the user with the command "COMM_RS232". The default value is <CR>, i.e. the ASCII carriage return character, the decimal value of which is 13.

Examples

GRID DUAL

This program message consists of a single command which instructs the instrument to display a dual grid. The terminator is not shown since it is usually automatically added by the interface driver routine which writes to the GPIB (or RS-232).

BWL ON; DISPLAY OFF; DATE?

This program message consists of two commands, followed by a query. They instruct the instrument to turn on the bandwidth limit, turn off the display, and then ask for the current date. Again, the terminator is not shown.

COMMAND/QUERY **FORM**

The general form of a command or a query consists of a command header <header> which is optionally followed by one or several parameters <data> separated by commas:

<header>[?] <data>,...,<data>

The notation [?] shows that the question mark is optional (turning the command into a query). The detailed listing of all commands in Section 5 indicates which commands may also be queries. There is a space between the header and the first parameter. There are commas between parameters.

Example

DATE 15,OCT,1989,13,21,16

This command instructs the oscilloscope to set its date and time to 15 OCT 1989, 13:21:16. The command header "DATE" indicates the action, the 6 data values specify it in detail.

Header

The header is the mnemonic form of the operation to be performed by the oscilloscope. All command mnemonics are listed in alphabetic order in Section 5.

The majority of the command/query headers have a long form for optimum legibility and a short form for better transfer and decoding speed. The two forms are fully equivalent and can be used interchangeably. For example, the following two commands for switching to the automatic trigger mode are fully equivalent:

TRIG_MODE AUTO and TRMD AUTO

Some command/query mnemonics are imposed by the IEEE 488.2 standard. They are standardized so that different instruments present the same programming interface for similar functions. All these mnemonics begin with an asterisk <*>, e.g. the command "*RST" is the IEEE 488.2 imposed mnemonic for resetting the instrument, whereas "*TST?" instructs the instru-

Header path

Some commands or queries apply to a sub-section of the oscilloscope, e.g. a single input channel or a trace on the display. In such cases, the header must be preceded by a path name that indicates the channel or trace to which the command applies. The header path normally consists of a 2-letter path name followed by a colon <:> which immediately precedes the command header.

ment to perform an internal self-test and to report the outcome.

Usually one of the waveform traces can be specified in the header path (refer to the individual commands listed in Section 5 for details on which values apply to a given command header):

Channels 1 and 2
Channels 3 and 4 (in 4-channel instruments)
Memory C and D
Function E and F
Expand A and B
External trigger

Example

C1:OFST -300 MV Set the offset of Channel 1 to -300 mV

Header paths need only be specified once. Subsequent commands whose header destination is not indicated are assumed to refer to the last defined path. For example, the following commands are identical:

C2:VDIV?; C2:OFST?	What is the vertical sensitivity and
	the offset of channel 2?

C2:VDIV?; OFST? Same as above, without repeating the path.

Data

Whenever a command/query uses additional data values, they are expressed in terms of ASCII characters. There is a single exception: the transfer of waveforms with the command/query "WAVEFORM", where the waveform may be expressed as a sequence of binary data values. Refer to Section 6 for a detailed explanation of the format of waveforms.

ASCII data can have the form of character, numeric, string or block data.

Character data

These are simple words or abbreviations for the indication of a specific action.

BANDWIDTH_LIMIT ON The data value "ON" indicates that the bandwidth limit should be turned on, rather than off.

In some commands, where as many as a dozen different parameters can be specified, or where not all parameters apply at the same time, the format requires pairs of data values. The first one names the parameter to be modified and the second gives its value. Only those parameter pairs to be changed need to be indicated.

HARDCOPY_SETUP_DEV,HP7470A,PORT,GPIB,PSIZE,A4

Three pairs of parameters are specified. The first specifies the device as the H7470A plotter (or compatible), the second indicates the GPIB port and the third requests the A4 format for paper size. While the command "HARDCOPY_SET-UP" allows many more parameters, they are either not relevant for plotters or they are left unchanged.

Numeric Data

The numeric data type is used to enter quantitative information. Numbers can be entered as integers, as fractions or in exponential representation.

EA:VPOS -5 Move the displayed trace of Expand A downwards by 5 divisions.

Set the DC offset of Channel 2 to 3.56 V. C2:OFST 3.56

TDIV 5.0E-6 Adjust the time base to 5 µsec/div.

Note: Numeric values may be followed by multipliers and units, modifying the value of the numerical expression. The following mnemonics are recognized:

EX	1E18	Exa-	PE	1E15	Peta-
T	1E12	Tera-	G	1E9	Giga-
MA	1E6	Mega-	K	1E3	kilo-
M	1E-3	milli-	U	1E-6	micro-
N	1E-9	nano-	PΙ	1E-12	pico-
F	1E-15	femto-	Α	1E-18	atto-

For example, there are many ways of setting the time base of the instrument to 5 usec/div:

TDIV 5E-6	Exponential notation, without any suffix.
TDIV 5 US	Suffix multiplier "U" for 1E-6, with the (optional) suffix "S" for seconds.

TDIV 5000 NS TDIV 5000E-3 US

String Data

This data type enables the transfer of a (long) string of characters as a single parameter. String data are formed by simply enclosing any sequence of ASCII characters between simple quotes.

MESSAGE 'Connect probe to point J3'

The instrument displays this message in the Message field above the grid.

Block Data

These are binary data values coded in hexadecimal ASCII, i.e. 4-bit nibbles are translated into the digits 0,...9, A,...F and transmitted as ASCII characters. They are only used for the transfer of waveforms (command "WAVEFORM") and of the instrument configuration (command "PANEL_SETUP")

RESPONSE MESSAGE FORM

The instrument sends a response message to the controller, as an answer to a query. The format of such messages is the same as that of program messages, i.e. individual responses in the format of commands, separated by semicolons <;> and ended by a terminator. They can be sent back to the instrument in the form in which they are received, and will be accepted as valid commands. In GPIB response messages, the <NL> <EOI> terminator is always

For example, if the controller sends the program message:

TIME DIV?;TRIG_MODE NORM;C1:COUPLING? (terminator not shown)

the instrument might respond as follows:

TIME DIV 50 NS;C1:COUPLING D50 (terminator not shown)

The response message only refers to the queries, i.e. "TRIG MODE" is left out. If this response is sent back to the instrument, it is a valid program message for setting its time base to 50 nsec/div and the input coupling of Channel 1 to 50 Ω .

Whenever a response is expected from the instrument, the control program must instruct the GPIB or RS-232-C interface to read from the instrument. If the controller sends another program message without reading the response to the previous one, the response message in the output buffer of the instrument is discarded.

The instrument uses somewhat stricter rules for response messages than for the acceptance of program messages. Whereas the controller may send program messages in upper or lower case characters, response messages are always returned in upper case. Program messages may contain extraneous spaces or tabs (white space), response messages do not. Whereas program messages may contain a mixture of short and long command/query headers, response messages always use short headers as a default. However, the instrument can be forced with the "COMM HEADER" to use long headers or no headers at all. If the response header is omitted, the response transfer time is minimized, but such a response could not be sent back to the instrument again. In this case suffix units are also suppressed in the response.

If the trigger slope of Channel 1 is set to negative, the query "C1:TRSL?" could yield the following responses:

C1:TRIG_SLOPE NEG header format: long C1:TRSL NEG header format: short NEG header format: off

Waveforms which are obtained from the instrument using the query "WAVEFORM?" constitute a special kind of response message. Their exact format can be controlled with the commands "COMM_FORMAT" and "COMM_ORDER", as explained in Section 6.

GPIB OPERATION

This section describes how to remotely control the oscilloscope via the GPIB. Topics discussed include interface capabilities, addressing, standard bus commands, and polling schemes.

GPIB STRUCTURE

The GPIB is like an ordinary computer bus, except that it interconnects independent devices via a cable bus whereas a computer has its circuit cards interconnected via a backplane bus. The GPIB carries program messages and interface messages:

- Program messages, often called device-dependent messages, contain programming instructions, measurement results, instrument status and waveform data. Their general form is described in Section 2.
- Interface messages manage the bus itself. They perform functions such as initializing the bus, addressing and unaddressing devices and setting remote and local modes.

Devices on the GPIB can be listeners, talkers, and/or controllers. A talker sends program messages to one or more listeners. A controller manages the flow of information on the bus by sending interface messages to the devices.

The oscilloscope can be a talker or a listener, but not a controller. The host computer, however, must be able to act as a listener, talker and controller. For details on how the controller configures the GPIB for specific functions, refer to the GPIB interface manufacturer's manual.

INTERFACE CAPABILITIES

The interface capabilities of the oscilloscope include the following IEEE 488.1 definitions:

AH1	Complete Acceptor Handshake
SH1	Complete Source Handshake
L4	Partial Listener Function
T5	Complete Talker Function
SR1	Complete Service Request Function
RL1	Complete Remote/Local Function
DC1	Complete Device Clear Function
DT1	Complete Device Trigger
PP1	Parallel Polling: remote configurability
C0	No Controller Functions
E2	Tri-state Drivers

ADDRESSING

Every device on the GPIB has an address. When the thumbwheel address switches on the rear panel of the oscilloscope are set to a value between 0 and 30, the instrument can be controlled via GPIB. When the switches are set to above 30, the instrument can execute talk-only operations on the GPIB, for example driving a GPIB plotter. In this case no controller is present and the instrument is directly connected to the plotter. Addresses above 30 also enable the instrument to be controlled via the RS-232-C port.

The instrument reads the address switches once at power on, or when the RESET button on the rear panel is pressed. If the address is changed during operation, the instrument must be powered again to enable the new address. The value of the GPIB address appears in the menu "Auxiliary Setups".

If the oscilloscope is addressed to talk, it will remain configured to talk until a universal untalk command (UNT), its own listen address (MLA), or another instrument's talk address is received.

Similarly, if the oscilloscope is addressed to listen, it will remain configured to listen until a universal unlisten command (UNL), or its own talker address (MTA) is received.

GPIB SIGNALS

The bus system consists of 16 signal lines and 8 ground or shield lines. The signal lines are divided into 3 groups:

- 8 data lines
- 3 handshake lines
- 5 interface management lines

Data Lines

The eight data lines, usually called DI01 through DI08, carry both program and interface messages. Most of the messages use the 7-bit ASCII code, in which case DI08 is unused.

Handshake Lines

These three lines control the transfer of message bytes between devices. The process is called a three-wire interlocked handshake and it guarantees that the message bytes on the data lines are sent and received without transmission error.

Interface Management Lines The following five lines manage the flow of information across the interface.

> ATN (ATteNtion): The controller drives the ATN line true when it uses the data lines to send interface messages such as talk and listen addresses or a device clear (DCL) message. When ATN is false, the bus is in the data mode for the transfer of program messages from talkers to listeners.

> IFC (InterFace Clear): The controller sets the IFC line true to initialize the bus.

REN (Remote ENable): The controller uses this line to place devices in remote or local program mode.

SRQ (Service ReQuest): Any device can drive the SRQ line true to asynchronously request service from the controller. This is the equivalent of a single interrupt line on a computer bus.

EOI (End Or Identify): This line has two purposes. The talker uses it to mark the end of a message string. The controller uses it to tell devices to identify their response in a parallel poll (discussed later in this section).

I/O Buffers

The instrument has a 256-byte input buffer and a 256-byte output buffer. An incoming program message is not decoded before a message terminator has been received. However, if the input buffer becomes full (because the program message is longer than the buffer), the instrument starts analyzing the message. In this case data transmission is temporarily halted, and the controller may generate a timeout if the limit was set too low.

IEEE 488.1 STANDARD MESSAGES

The IEEE 488.1 standard specifies not only the mechanical and electrical aspects of the GPIB, but also the low-level transfer protocol, e.g. it defines how a controller addresses devices, turns them into talkers or listeners, resets them or puts them in the remote state. Such interface messages are executed with the interface management lines of the GPIB, usually with ATN true.

All of these messages (except GET) are executed immediately upon reception and not in chronological order with normal commands.

Note: In addition to the IEEE 448.1 interface message standards, the new IEEE 488.2 standard specifies some standardized program messages, i.e. command headers. They are identified with a leading asterisk <*> and are listed among the commands in Section 5.

The command list in Section 5 does not contain any command for clearing the input/output buffers or for setting the instrument to the remote state. This is because such commands are already specified as IEEE 488.1 standard messages. Refer to the GPIB interface manual of the host controller as well as to its support programs which should contain special calls for the execution of these messages.

The following describes those IEEE 488.1 standard messages which go beyond mere reconfiguration of the bus and which have an effect on the operation of the instrument.

Device Clear

In response to a universal Device CLear (DCL) or a Selected Device Clear message (SDC), the oscilloscope clears the input/output buffers, aborts the interpretation of the current command (if any) and clears any pending commands. Status registers and status enable registers are not cleared. Although DCL has an immediate effect it can take several seconds to execute this command if the instrument is busy.

Group Execute Trigger

The Group Execute Trigger message (GET) causes the oscilloscope to arm the trigger system. It is functionally identical to the "*TRG" command.

Remote ENable

This interface message is executed when the controller holds the Remote ENable control line (REN) true and configures the instrument as a listener. The REMOTE LED on the front panel lights up to indicate that the instrument is set to the remote mode. All the front–panel controls are disabled except the left–hand menu buttons, the intensity controls and the LOCAL button. The menu indications on the left–hand side of the screen no longer appear since menus cannot now be operated manually. Whenever the controller returns the REN line to false, all instruments on the bus return to LOCAL. Individual instruments can be returned to LOCAL with the Go To Local message (see below).

As a rule, remote commands are only executed when the instrument is in the remote state, whereas queries are always executed. Local front-panel control may be regained by pressing the LOCAL push button, unless the instrument was placed in the Local LOckout (LLO) mode.

Local LOckout

The Local LOckout command (LLO) causes the LOCAL button on the front panel of the oscilloscope to be disabled. The LLO command can be sent in local or remote mode but only becomes effective once the instrument has been set to the remote mode.

Go To Local

The Go To Local message (GTL) causes the instrument to return to the local mode. All front-panel controls become active and the menus on the left-hand side of the screen reappear. Thereafter, whenever the instrument is addressed as a listener it will be immediately set to the remote state again.

Note that a GTL message does not clear the local lockout if it was set. Thus, whenever the instrument returns to the remote state the local lockout mode would immediately be effective again.

A command string should not be immediately followed by a GTL message. Since GTL is executed at once, the instrument may already be returned to the local state before the commands in the

input buffer are interpreted. Therefore, the instrument may refuse to execute them if they require the instrument to be in REMOTE. A safe way to ensure that all commands have been interpreted is to append a query (e.g. "*STB?") to the command string and to wait for the response before sending a GTL.

InterFace Clear

The InterFace Clear message (IFC) initializes the GPIB but has no effect on the operation of the oscilloscope.

PROGRAMMING GPIB TRANSFERS

To illustrate the GPIB programming concepts a number of examples written in BASICA are included in this section. It is assumed that the controller is IBM-PC compatible, running under DOS, and that it is equipped with a National Instruments² GPIB interface card. GPIB programming with other languages such as C or Pascal is quite similar.

If you use another computer or another GPIB interface, refer to the interface manual for installation procedures and subroutine calls similar to those described here.

Configuring the **GPIB** Hardware

Check that the GPIB interface is properly installed in the computer. If it is not, follow the installation instructions of the interface manufacturer. In the case of the National Instruments interface, it is possible to modify the base I/O address of the board, the DMA channel number and the interrupt line setting using switches and jumpers. In our program examples, they are assumed to be left in their default positions.

Connect the oscilloscope to the computer with a GPIB interface cable. Set the GPIB address on the rear of the instrument to the required value. The program examples assume that it is set to 4. Remember to power the instrument up after setting the GPIB address.

Configuring the **GPIB** Driver Software

The host computer needs an interface driver which handles the transactions between the user's programs and the interface board. In the case of the National Instruments interface, the installation procedure:

- copies the GPIB handler GPIB.COM into the boot directory.
- modifies the DOS system configuration file CONFIG.SYS to declare the presence of the GPIB handler.
- 2. National Instruments Corporation, 12109 Technology Boulevard, Austin, Texas 78727

- creates a sub-directory GPIB-PC.
- installs in GPIB-PC a number of files and programs which are useful for testing and reconfiguring the system, and for writing user programs.

The following files in the sub-directory GPIB-PC are of particular use:

IBIC.EXE allows interactive control of the GPIB via functions entered at the keyboard. Use of this program is highly recommended to anyone who is not familiar with GPIB programming or with the oscilloscope's remote commands. An example of the use of IBIC.EXE is shown in Appendix A.

DECL.BAS is a declaration file that contains code to be included at the beginning of any BASICA application program. Simple application programs can be quickly written by appending the user's instructions to DECL.BAS and executing the complete file.

IBCONF.EXE is an interactive program which allows inspection or modification of the current settings of the GPIB handler. To run IBCONF.EXE, refer to the National Instruments user's manual.

In the program examples in this section, it is assumed that the National Instruments GPIB driver GPIB.COM is in its default state, i.e. that the user has not modified it with IBCONF.EXE. This means that the interface board can be referred to by the symbolic name 'GPIB0' and that devices on the GPIB bus with addresses between 1 and 16 can be called by the symbolic names 'DEV1' to 'DEV16'.

Note: If you have a National Instruments PC2 interface card rather than PC2A, you must run IBCONF to declare the presence of this card rather than the default PC2A.

Simple Transfers

For a large number of remote control operations it is sufficient to use just 3 different subroutines (IBFIND, IBRD and IBWRT) provided by National Instruments. The following complete program reads the time-base setting of the oscilloscope and displays it on the terminal:

1-99	<decl.bas></decl.bas>
100	DEV\$="DEV4"
110	CALL IBFIND(DEV\$,SCOPE%)
120	CMD\$="TDIV?"
130	CALL IBWRT(SCOPE%, CMD\$)
140	CALL IBRD(SCOPE%,RD\$)
150	PRINT RD\$
160	END

Explanation

Lines 1 - 99 are a copy of the file DECL.BAS supplied by National Instruments. The first 6 lines are required for the initialization of the GPIB handler. The other lines are declarations which may be useful for larger programs, but are not really required code. The sample program above only uses the strings CMD\$ and RD\$ which are declared in DECL.BAS as arrays of 255 characters.

Note: DECL.BAS requires access to the file BIB.M during the GPIB initialization. BIB.M is one of the files supplied by National Instruments, and it must exist in the directory currently in use.

Note: The first 2 lines of DECL.BAS each contain a string "XXXXX" which must be replaced by the number of bytes which determine the maximum workspace for BASICA (computed by subtracting the size of BIB.M from the space currently available in BASICA). For example, if the size of BIB.M is 1200 bytes and when BASICA is loaded it reports "60200 bytes free", you should replace "XXXXX" by the value 59000 or less.

Lines 100 and 110 open the device "DEV4" and associate with it the descriptor "SCOPE%". All I/O calls from now on will refer to "SCOPE%". The default configuration of the GPIB handler recognizes "DEV4" and associates with it a device with GPIB address 4. If you want to use another GPIB address between 1 and 16, use the string "DEVx" with x = 1...16. If you want to use another name, run IBCONF.EXE to declare this name to the handler.

Lines 120 and 130 prepare the command string TDIV? and transfer it to the instrument. The command instructs it to respond with the current setting of the time base.

Line 140 reads the response of the instrument and places it into the character string RD\$.

Line 150 displays the response on the terminal.

When running this sample program, the oscilloscope will automatically be set to the remote state when IBWRT is executed, and will remain in that state. Pressing the LOCAL button on the front panel will return the oscilloscope to local mode if the GPIB handler was modified to inhibit Local LOckout (LLO).

Here is a slightly modified version of the sample program which checks if any error occurred during GPIB operation:

1-99	<decl.bas></decl.bas>
100	DEV\$="DEV4"
110	CALL IBFIND(DEV\$,SCOPE%)
120	CMD\$="TDIV?"
130	CALL IBWRT(SCOPE%,CMD\$)
140	IF ISTA% < 0 THEN GOTO 200
150	CALL IBRD(SCOPE%,RD\$)
160	IF ISTA% < 0 THEN GOTO 250
170	PRINT RD\$
180	IBLOC(SCOPE%)
190	END
200	PRINT "WRITE ERROR = ";IBERR%
210	END
250	PRINT "READ ERROR = ";IBERR%
260	END

The GPIB status word ISTA%, the GPIB error variable IBERR% and the count variable IBCNT% are defined by the GPIB handler and are updated with every GPIB function call. Refer to the National Instruments user's manual for details. The sample program above would report if the GPIB address of the instrument was set to a value other then 4. Line 180 resets the instrument to local with a call to the GPIB routine IBLOC.

Example 2 in Appendix A provides a more useful program which enables interactive setting and inspection of the front-panel controls as well as archiving and recalling of waveforms. Note that this program is written with just 7 different GPIB calls.

Some Additional Driver Calls

IBLOC is used to execute the IEEE 488.1 standard message Go To Local (GTL), i.e. it returns the instrument to the local state. The programming example above shows its use.

IBCLR executes the IEEE 488.1 standard message Selected Device Clear (SDC).

IBRDF and IBWRTF allow data to be read from GPIB to a file and data to be written from a file to GPIB respectively. Transferring data directly to or from a storage device does not limit the size of the data block, but it may be slower than transferring to the computer memory. Example 2 in Appendix A shows the use of these calls.

IBRDI and IBWRTI allow data to be read from GPIB to an integer array and data to be written from an integer array to GPIB. Since the integer array allows storage of up to 64 kilobytes (in BASIC), IBRDI and IBWRTI should be used for the transfer of large

data blocks to the computer memory, rather than IBRD or IBWRT which are limited to 256 bytes by the BASIC string length. Note that IBRDI and IBWRTI only exist for BASIC, since the function calls IBRD and IBWRT for more modern programming languages, such as C, are much less limited in the data block size.

IBTMO can be used to change the time-out value during program execution. The default value of the GPIB driver is 10 seconds, e.g. if the instrument does not respond to a IBRD call, IBRD will return with an error after the specified time.

IBTRG executes the IEEE 488.1 standard message Group Execute Trigger (GET), which causes the oscilloscope to arm the trigger system.

National Instruments supply a number of additional function calls. In particular, it is possible to use the so-called board level calls which allow a very detailed control of the GPIB. The use of such calls is shown in Example 3 of Appendix A.

PROGRAMMING SERVICE REQUESTS

When an oscilloscope is used in a remote application, events often occur asynchronously, i.e. at times that are unpredictable for the host computer. The most common case is waiting for a trigger after the instrument has been armed. The controller must wait until the acquisition is finished before it can read the acquired waveform. The simplest way of checking if a certain event has occurred is by continuously or periodically reading the status bit associated with it until the required transition is detected. Continuous status bit polling is described in more detail in the sub-section "Instrument Polls". For a complete explanation of the status bytes refer to Section 7.

A potentially more efficient way of detecting events occurring in the instrument is the use of the Service Request (SRQ). This GPIB interrupt line can be used to interrupt program execution in the controller. Therefore, the controller can execute other programs while waiting for the instrument. Unfortunately, not all interface manufacturers support the programming of interrupt service routines. In particular, National Instruments only supports the SRQ bit within the ISTA% status word. This requires the user to continuously or periodically check this word, either explicitly or with the function call IBWAIT. In the absence of real interrupt service routines the use of SRQ may not be very advantageous.

In the default state, after power-on, the Service ReQuest is disabled. The SRQ is enabled by setting the Service Request Enable register with the command "*SRE" and specifying which event should generate an SRQ. The oscilloscope will interrupt the controller as soon as the selected event(s) occur by asserting the SRQ interface line. If several devices are connected to the GPIB, the controller may have to identify which instrument caused the interrupt by serial polling the various devices.

Note: The SRQ bit is latched until the controller reads the STatus Byte Register (STB). The action of reading the STB with the command "*STB?" clears the register contents except the MAV bit (bit 4) until a new event occurs. Service requesting may be disabled by clearing the SRE register ("*SRE 0").

Example 1

To assert SRQ in response to the events "new signal acquired" or "return-to-local" (pressing the front-panel button LOCAL).

These events are tracked by the INR register which is reflected in the SRE register as the INB summary bit in position 0. Since the bit position 0 has the value 1, the command "*SRE 1" enables the generation of SRQ whenever the INB summary bit is set.

In addition, the events of the INR register which may be summarized in the INB bit must be specified. The event "new signal acquired" corresponds to INE bit 0 (value 1) while the event "return-to-local" is assigned to INE bit 2 (value 4). The total sum is 1+4=5. Thus the command "INE 5" is needed.

CMD\$="INE 5:*SRE 1"

CALL IBWRT(SCOPE%, CMD\$)

Example 2

To assert SRQ when soft key 10 is pressed.

The event "soft key 10 pressed" is tracked by the URR register. Since the URR register is not directly reflected in STB but only in the ESR register (URR, bit position 6), the ESE enable register must be set first with the command "*ESE 64" to allow the URQ setting to be reported in STB. An SRQ request will now be generated provided that the ESB summary bit (bit position 5) in the SRE enable register is set ("*SRE 32").

CMD\$="*ESE 64;*SRE 32"

CALL IBWRT(SCOPE%, CMD\$)

INSTRUMENT POLLS

State transitions occurring within the instrument can be remotely monitored by polling selected internal status registers. This subsection discusses a number of polling methods which may be used to detect the occurrence of a given event.

- 1. Continuous poll
- 2. Serial poll
- 3. Parallel poll
- 4. *IST poll

To emphasize the differences between these methods, the same example will be presented in each case, i.e. determining if a new acquisition has taken place. By far the simplest poll is the continuous poll. The other methods only make sense if interrupt service routines (servicing the SRQ line) are supported or if multiple devices on GPIB must be monitored simultaneously.

Continuous Poll

In continuous polling a status register is continuously monitored until a transition is observed. This is the most straightforward method for detecting state changes but may be impracticable in some situations, especially in multiple device configurations.

In the following example, the event "new signal acquired" is observed by continuously polling the INternal state change Register (INR) until the corresponding bit (in this case bit 0, i.e. value 1) is non-zero to indicate that a new waveform has been acquired. Reading INR clears it at the same time so that there is no need for an additional clearing action after a non-zero value has been detected. The command "CHDR OFF" instructs the instrument to omit any command headers when responding to a query. This simplifies the decoding of the response. The instrument would therefore send "1" rather than "INR 1".

```
CMD$="CHDR OFF"
CALL IBWRT(SCOPE%, CMD$)
MASK\% = 1
                        'New Signal Bit has value 1
LOOP\% = 1
WHILE LOOP%
         CMD$="INR?"
         CALL IBWRT(SCOPE%,CMD$)
         CALL IBRD(SCOPE%, RD$)
         NEWSIG% = VAL(RD$) AND MASK%
         IF NEWSIG% = MASK% THEN LOOP% = 0
WEND
```

Serial Poll

Serial polling takes place once the SRQ interrupt line has been asserted. The controller examines which instrument has generated the interrupt by inspecting the SRQ bit in the STB register of each instrument. Because service request is based on an interrupt mechanism, serial polling offers a reasonable compromise in terms of servicing speed in multiple device configurations.

In the following example, the command "INE 1" enables the event "new signal acquired" to be reported in the INR to the INB bit of the status byte STB. The command "*SRE 1" enables the INB of the status byte to generate an SRQ whenever it is set. The function call IBWAIT instructs the computer to wait until one of three conditions occur: &H8000 in the mask (MASK%) corresponds to a GPIB error, &H4000 to a time-out error and &H0800 to the detection of RQS (ReQuest for Service generated by the SRQ bit).

Whenever IBWAIT detects RQS it automatically performs a serial poll to find out which instrument generated the interrupt. It will only exit if there was a time-out or if the instrument "SCOPE%" generated SRQ. The additional function call IBRSP fetches the value of the status byte which may be further interpreted. For this example to function properly the value of 'Disable Auto Serial Polling' must be set 'off' in the GPIB handler (use IBCONF.EXE to check).

```
CMD$="*CLS; INE 1; *SRE 1"
CALL IBWRT(SCOPE%,CMD$)
MASK% = &HC800
CALL IBWAIT(SCOPE%,MASK%)
IF (IBSTA% AND &HC000) <> 0 THEN PRINT "GPIB or Time-out Error" : STOP
CALL IBRSP(SCOPE%,SPR%)
PRINT "Status Byte = ", SPR%
```

Note: After the serial poll is completed, the RQS bit in the STB status register is cleared. Note that the other STB register bits remain set until they are cleared by means of a "*CLS" command or the instrument is reset. If these bits are not cleared, they cannot generate another interrupt.

Serial polling is only an advantage if there are several instruments that may need attention. Board-level function calls can deal simultaneously with several instruments attached to the same interface board. Refer to the National Instruments user's manual.

Parallel Poll

Parallel polling is only an advantage if there are several instruments that may need attention.

In parallel polling, the controller simultaneously reads the Individual STatus bit (IST) of all the instruments to determine which one needs service. Since parallel polling allows up to eight different instruments to be polled at the same time, parallel polling is the fastest way to identify state changes of instruments supporting this capability.

When a parallel poll is initiated, each instrument returns a status bit via one of the DIO data lines. Devices may respond either individually using a separate DIO line or collectively on a single data line. Data line assignments are made by the controller via a Parallel Poll Configure (PPC) sequence.

In the following example, the command "INE 1" enables the event "new signal acquired" in the INR to be reported to the INB bit of the status byte STB. The PaRallel poll Enable register (PRE) determines which events will be summarized in the IST status bit. The command "*PRE 1" enables the INB bit to set the IST bit whenever it is set. Once parallel polling has been established, the parallel poll status is examined until a change on data bus line DI02 takes place.

Stage 1: Enable the INE and PRE registers, configure the controller for parallel poll and instruct the oscilloscope to respond on data line 2 (DI02)

CMD1\$="?_@\$"
CALL IBCMD(BRD0%,CMD1\$)
CMD\$="INE 1;*PRE 1"
CALL IBWRT(BRD0%,CMD\$)
CMD4\$=CHR\$(&H5)+CHR\$(&H69)+"?"
CALL IBCMD(BRD0%,CMD4\$)

Stage 2: Parallel poll the instrument until DI02 is set

LOOP% = 1 WHILE LOOP%

CALL IBRPP(BRD0%,PPR%)
IF (PPR% AND &H2) = 2 THEN LOOP% = 0

WEND

Stage 3: Disable parallel polling (hex 15) and clear the parallel poll register ${\bf P}$

CMD5\$=CHR\$(&H15) CALL IBCMD(BRD0%,CMD5\$) CALL IBCMD(BRD0%,CMD1\$) CMD\$="*PRE 0" CALL IBWRT(BRD0%,CMD\$)

Note 1: In the example above, board-level GPIB function calls are used. It is assumed that the controller (board) and oscilloscope (device) are respectively located at addresses 0 and 4. The listener and talker addresses for the controller and oscilloscope are:

Logic device	Listener address	Talker address
controller	32 (ASCII <space>)</space>	64 (ASCII @)
oscilloscope	32+4=36 (ASCII \$)	64+4=68 (ASCII D)

Note 2: The characters "?" and "_" appearing in the command strings stand for unlisten and untalk respectively. They are used to set the devices to a "known" state.

Note 3: To shorten the size of the program examples, device talking and listening initialization instructions have been grouped into character chains. They are:

CMD1\$ = "?_@\$" 'Unlisten, Untalk, PC talker, DSO listener

Note 4: The remote message code for executing a parallel response in binary form is 01101PPP where PPP specifies the data line. Since data line 2 is selected, the identification code is 001 which results in the code 01101001 (binary) or &H69 (hex). See Table 38 of the IEEE 488-1978 Standard for further details.

*IST Poll

The state of the Individual STatus bit (IST) returned in parallel polling can also be read by sending the "*IST?" query. To enable this poll mode, the oscilloscope must be initialized as for parallel polling by writing into the PRE register. Since *IST polling emulates parallel polling, this method is applicable in all instances where parallel polling is not supported by the controller.

In the following example, the command "INE 1" enables the event "new signal acquired" in the INR to be reported to the INB bit of the status byte STB. The command "*PRE 1" enables the INB bit to set the IST bit whenever it is set. The command "CHDR OFF" suppresses the command header in the response of the instrument, simplifying the interpretation. The status of the IST bit is then continuously monitored until it is set by the instrument.

```
CMD$="CHDR OFF; INE 1; *PRE 1"
CALL IBWRT(SCOPE%,CMD$)
LOOP\% = 1
WHILE LOOP%
         CMD$="*IST?"
         CALL IBWRT(SCOPE%, CMD$)
         CALL IBRD(SCOPE%, RD$)
         IF VAL(RD\$) = 1 THEN LOOP% = 0
WEND
```

DRIVING A HARD-COPY DEVICE

The oscilloscope can be interfaced to a wide range of plotters and printers and be instructed to directly plot or print the screen contents onto these devices. The devices supported by the unit are listed with the command "HARDCOPY SETUP" in Section 5.

When the hard-copy device is connected to the GPIB two different configurations should be considered depending on whether or not a GPIB controller is available.

Plotting/Printing without a GPIB Controller

When only the oscilloscope and the hard-copy device are connected to the GPIB, the oscilloscope must be configured as talker-only and the hard-copy device as listener-only to ensure proper data transfer. The oscilloscope can be configured as a talker-only by using the thumbwheel switch at the rear of the instrument to select an address larger than 30. The hard-copy device manufacturer usually specifies an address which forces the instrument into the listening mode.

- Select the oscilloscope's address to be larger than 30.
- Switch on the oscilloscope.
- Configure the "Hardcopy" sub menu in the "Auxiliary Setups" menu specifying "GPIB" as hard copy port.
- Put the hard-copy device in listener-only mode.
- Press the screen dump button on the front panel of the instrument.

Plotting/Printing with a GPIB Controller

If a controller is connected to the GPIB, data transfers must be supervised by the controller. The oscilloscope must be set to an address between 0 and 30 which differs from the controller's and the hard-copy device's address. Different schemes can be used to transfer the screen contents:

- 1. The controller reads the data into internal memory and then sends them to the printer/plotter. This alternative can be done with simple high-level GPIB function calls.
- 2. The oscilloscope sends data to both the controller and the printer/plotter.
- The controller goes into a standby state. The oscilloscope becomes a talker and sends data directly to the printer/plotter.

1. Data read by controller and sent to printer/plotter

The controller stores the full set of printer/plotter instructions and sends them afterwards to the graphics device. This method is the most straightforward way of transferring screen contents but it requires a large amount of buffer storage (110K for 4 traces).

CMD\$ = "SCDP"

CALL IBWRT(SCOPE%,CMD\$)

FILE\$="PLOT.DAT"

CALL IBRDF(SCOPE%,FILE\$)

CALL IBWRTF(PLOTTER%,FILE\$)

2. Oscilloscope sends data to controller and printer/plotter

The oscilloscope puts the printer/plotter instructions on to the bus. The data is directly plotted out and saved in scratch memory in the controller. The contents of the scratch file can be deleted later on.

Stage 1: Controller talker, oscilloscope listener. Issue the screen dump command

CMD1\$="?_@\$": CALL IBCMD(BRD0%,CMD1\$)
CMD\$="SCDP": CALL IBWRT(BRD0%,CMD\$)

Stage 2: Oscilloscope talker, controller and plotter listeners. Plot data while storing data in scratch file SCRATCH.DAT

CMD2\$="?_ D%": CALL IBCMD(BRD0%,CMD2\$)

FILE\$="SCRATCH.DAT": CALL IBRDF(BRD0%,FILE\$)

3. Oscilloscope talks directly to plotter/printer

The controller goes into stand-by and resumes GPIB operations once the data have been plotted, that is when an EOI is detected.

Stage 1: Controller talker, oscilloscope listener. Issue the screen dump command

CMD1\$="?_@\$": CALL IBCMD(BRD0%,CMD1\$) CMD\$="SCDP": CALL IBWRT(BRD0%,CMD\$)

Stage 2: Oscilloscope talker, plotter listener. Put controller in stand-by

CMD2\$="? D%": CALL IBCMD(BRD0%,CMD2\$)

V%=1: CALL IBGTS(BRD0%,V%)

Note 1: In schemes 2 and 3, board-level GPIB function calls are used. It is assumed that the controller (board), the oscilloscope and the plotter are respectively located at addresses 0, 4 and 5. The listener and talker addresses for the controller, oscilloscope and plotter are:

Logic device	Listener address	Talker address	
controller	32 (ASCII <space>)</space>	64 (ASCII @)	
oscilloscope	32+4=36 (ASCII \$)	64+4=68 (ASCII D)	
hard-copy dev.	32+5=37 (ASCII %)	64+5=69 (ASCII E)	

Note 2: The characters "?" and "_" appearing in the command strings stand for unlisten and untalk respectively. They are used to set the devices to a "known" state.

Note 3: To shorten the size of the program examples, device talking and listening initialization instructions have been grouped into character chains. They are:

CMD1\$ = "? @\$" 'Unlisten, Untalk, PC talker, DSO listener CMD2\$ = "? D" 'Unlisten, Untalk, PC listener, DSO talker

		Prido
		PS (grahama distinguismon variantes
		Parameter and pa
		No9 featingenoenos
		!
		44.0
		and the second second
		The second second
		-

RS-232-C OPERATION

INTRODUCTION

LeCroy oscilloscopes may be remotely controlled using a host, either a terminal or a computer, via the RS-232-C port. For this purpose the oscilloscope must be set at an address higher than 30 using the thumbwheel switch at the rear of the instrument.

All the commands described in Section 5 are supported but waveform transfer is only possible in HEX mode. The default value for COMM_FORMAT is set appropriately. The syntax of the response to WF? is identical to the GPIB case.

In this section some special RS-232-C commands are defined either for configuring the oscilloscope, or simulating GPIB 488.1 messages such as setting the oscilloscope into remote or local modes.

Notation

Throughout this section, characters which cannot be printed in ASCII will be represented by their mnemonics.

Example

<LF> is the ASCII line feed character whose decimal value is 10

<BS> is the ASCII backspace character whose decimal value

CTRL_U means that the control key and the U key are pressed simultaneously.

RS-232-C PIN ASSIGNMENTS

The remote RS-232-C pin assignments (indicated on the rear panel) are as follows:

Pin #		Description
2	$T \times D$	Transmitted data (from the oscilloscope).
3	$R \times D$	Received data (to the oscilloscope).
4	RTS	Request to send (from the oscilloscope). If the software Xon/Xoff handshake is selected it is always TRUE. Otherwise (hardware handshake) it is TRUE when the oscilloscope is able to receive characters and FALSE when the oscilloscope is unable to receive characters.
5	CTS	Clear to send (to the oscilloscope). When true, the oscilloscope can transmit, when false, transmission stops. It is used for the oscilloscope output hardware handshake.
20	DTR	Data terminal ready (from oscilloscope). Always TRUE.

- 1 **GND** Protective Ground.
- 7 SIG GND Signal Ground.

RS-232-C CONFIGURATION

The RS-232-C port is configured in full duplex. This means that the two sides (i.e. the controller and the oscilloscope) can both send and receive messages at the same time. However, when the oscilloscope receives a new command, it stops outputting.

Transmission of long messages to the oscilloscope should be done while the oscilloscope is in a triggered mode with no acquisition in progress. This is especially important when sending waveforms or front-panel setups into the oscilloscope.

The behavior of the RS-232-C port may be set according to the user's needs. For this purpose, in addition to the basic setup on the front-panel menu there are "immediate commands" as well as a special command "COMM RS232". Immediate commands consist of the ASCII ESCape character <ESC> (whose decimal value is 27), followed by another character. Such commands are interpreted as soon as the second character has been received.

Note: The RS-232-C baud rate, parity, character length and number of stop bits are among the parameters that are saved or recalled by the front-panel "SAVE" or "RECALL" button, or by the remote commands "*SAV", "*RCL" or "PANEL SETUP". When recalling, care must be taken to ensure that these parameters are set at the same value as the actual ones. Otherwise, the host may no longer be able to communicate with the oscilloscope and a manual reconfiguration would be necessary.

Echo of Received Characters by the Oscilloscope

The serial port may echo the received characters. Echo is useful if the oscilloscope is attached to a terminal. Echoing can be turned on or off by sending the two character sequence <ESC>] or <ESC>[respectively. Echoing is on by default.

Note: The host must not echo characters received from the oscilloscope.

Handshake Control

When the oscilloscope input buffer becomes almost full, the instrument sends a handshake signal to the host telling it to stop transmitting. When this buffer has enough room to receive more characters another handshake signal will be sent. The handshake signals are either the CTRL-S (or <XOFF>) and CTRL-Q (<XON>) characters or a signal level on the RTS line (pin 4). This is selected by sending the two-character sequence <ESC>) for XON/XOFF handshake - this is the default - or <ESC>(for RTS handshake.

The flow of characters coming from the oscilloscope may be controlled either by a signal level on the CTS line (pin 5) or by the <XON>/<XOFF> pair of characters.

Editing Features

When the oscilloscope is directly connected to a terminal, the following features will facilitate the correction of typing errors:

<BS> or <DELETE>

Delete the last character.

CTRL U

Delete the last line.

Message Terminators

"Message terminators" are markers that indicate to the receiver that a message has been completed.

On input to the oscilloscope, the Program Message Terminator is one character which can be selected by the user. A good choice would be a character that is never used for anything else. The character is chosen using the command COMM_RS232 and the keyword EI. The default Program Message Terminator is the ASCII character <CR>, whose decimal value is 13.

The oscilloscope appends a Response Message Terminator to the end of each of its responses. It is a string, like a computer prompt, chosen by the user. This string must not be empty. The default Response Message Terminator is "\n\r" which means <LF><CR>.

Examples

(1) COMM RS232 EI,3

This command informs the oscilloscope that each message it receives will be terminated with the ASCII character <ETX> which corresponds to 3 in decimal.

(2) COMM_RS232 EO,"\r\nEND\r\n"

This command indicates to the oscilloscope that it must append the string "\r\nEND\r\n" to each response.

After these settings, a host command will look like:

TDIV?<ETX>

The oscilloscope responds:

TDIV 1. S

END

Note: Having sent a COMM_RS232 command, the host must wait for the oscilloscope to change its behavior before sending a command in the new mode. A safe way to do this is to include a query on the line which contains the COMM_RS232 command and wait until the response is received. For example,

COMM RS232 EI,3; *STB?

SRQ Message

Each time the Master Summary Status (MSS) bit of the STatus Byte (STB) is set, the SRQ message (a string of characters) is sent to the host to indicate that the oscilloscope requests service. The RS-232-C SRQ message has the same meaning as the GPIB SRQ message. If the string is empty, no message will be sent. This is the default setting. Note that no response message terminator is added at the end of the SRQ message.

Example

COMM_RS232 SRQ,"\r\n\nSRQ\r\n\a"

When the MSS bit is set, the oscilloscope will send

a <CR> followed by 2 <LF>s SRQ

a <CR> followed by 1 <LF> and the buzer will sound.

Long Line Splitting

Line splitting is a feature provided for hosts that cannot accept lines with more than a certain number of characters. The oscilloscope may be configured to split responses into many lines. This feature is very useful for waveform or front—panel setup transfers although it is applicable to all response messages. Two parameters control this feature:

Line Separator: Off

messages will not be split into lines

<CR>,<LF> or <CR><LF> possible line terminators.

Line length:

the maximum number of characters in a line.

Example

COMM_RS232 LS,LF,LL,40

The line separator is the ASCII character <LF>, the line is a maximum of 40 characters long (excluding the line separator).

If the oscilloscope receives the command PNSU?, it may answer:

PNSU #9000001496

. . .

Remarks

Long commands sent to the oscilloscope may not be split into lines. If a command sent to the oscilloscope is the response to a previous query, the line split characters (<LF> and/or <CR>) must be removed.

This also applies to line split characters inside strings sent to the oscilloscope.

However, hex-ASCII data sent to the oscilloscope may contain line split characters. If you wish to use line splitting, ensure that neither the input message terminator characters nor the line split characters occur in the data.

COMMANDS SIMULATING GPIB COMMANDS

<ESC>C or <ESC>c Device clear command.

This command clears the input and output buffers. It has the same meaning as the GPIB DCL or SDC interface messages.

<ESC>R or <ESC>r Set to remote command (REN)

This command puts the oscilloscope into the remote mode. Its function is the same as GPIB asserting the REN line and setting the oscilloscope to listener.

<ESC>L or <ESC>l Set to local command

This command puts the oscilloscope into local mode. It clears local lockout. It has the same function as GPIB setting the REN line to false.

<ESC>F or <ESC>f
Set local lockout command

This command disables the front-panel "LOCAL" button either immediately if the oscilloscope is already in the remote mode or later when the oscilloscope is next set to remote control. This disabling of the front-panel "LOCAL" button is called "Local Lockout" and can only be cancelled with the <ESC>L command. <ESC>F has the same meaning as the GPIB LLO interface message.

<ESC>T or <ESC>t
Trigger command (GET)

This command rearms the oscilloscope while it is in "SINGLE" or in "SEQUENCE" mode (valid only while the oscilloscope is in the remote mode). It has the same meaning as the "*TRG" command, and also the same meaning as the GPIB GET interface message.

	- Add-
	now may have been been also been been been been been been been bee
	ALGERIAN CONTRACTOR
	American Marian
	N. Milanara
	objectives del pro-e-
	ry a nagari finaligicata
,	School Common William - Village - Vi
	Do-Lought and an
	The second secon
	Assessment
	}
	a) is the second
	* Registered
	1
	· v
	. Charleston
	The state of the s
	-
	enter de la constitución de la c
	and the second
	and the second
	-

SYSTEM COMMANDS

ORGANIZATION

This section of the manual lists all commands and queries recognized by the oscilloscope. For easy reference the listings are arranged in alphabetical order. Each command starts on a new page and the name (header) of the command is given in both the long and short forms. Below each name (header) it is indicated whether it denotes a command only, a command as well as a query, or a query only. For those headers that may be used to command an action, for example to modify a setup parameter, or to obtain some information such as the current value of a setup parameter, the query form is derived by appending a question mark (?) immediately to the header without intervening spaces.

The description of each command starts with a short explanation of the function performed by it, followed by a presentation of the formal syntax. In the formal syntax the header appears in mixed mode characters with the characters used to construct the short form shown in upper case.

Where applicable, the syntax of the query form is given along with the format of the response the oscilloscope will produce.

For most commands the description terminates with a short example illustrating a typical use of the command. The GPIB examples assume that the controller is equipped with a National Instruments interface board, and they show calls to the National Instruments interface subroutines in BASIC. The device name of the oscilloscope has been defined as "SCOPE%".

COMMAND SUMMARY

The following is an overview of the commands grouped according to their functionality.

Acquisition

To control the acquisition of waveforms:

ARM_ACQUISITION, AUTO_SETUP, BANDWIDTH_LIMIT, INTERLEAVED, SAMPLE_CLOCK, SEGMENTS, STOP, *TRG, WAIT.

To select vertical input parameters to capture waveforms: ATTENUATION, COUPLING, OFFSET, VOLT_DIV.

To select time-base parameters to capture waveforms: TIME DIV, TRIG_DELAY.

To select trigger conditions to capture waveforms: TRIG_COUPLING, TRIG_LEVEL, TRIG_MODE, TRIG_PATTERN, TRIG_SELECT, TRIG_SLOPE.

Communication

To set communication characteristics:

COMM_FORMAT, COMM_HEADER, COMM_HELP, COMM_ORDER, COMM_RS232.

Cursor To perform measurements:

CURSOR MEASURE, CURSOR SET, CURSOR VALUE?,

PARAMETER_VALUE?, XY_CURSOR_ORIGIN, XY_CURSOR_SET, XY_CURSOR_VALUE?.

Display To display waveforms:

DISPLAY, DUAL_ZOOM, GRID, HOR_MAGNIFY,

HOR_POSITION, INTENSITY, MULTI_ZOOM, SELECT, TRACE, VERT_MAGNIFY, VERT_POSITION, XY_ASSIGN,

XY DISPLAY, ZOOM.

To display messages to a local user: CALL_HOST, KEY, MESSAGE.

Function To perform mathematical operations on waveforms:

DEFINE, FUNCTION_RESET, FUNCTION_STATE.

Hard Copy To plot or print the contents of the display screen:

HARDCOPY_SETUP, HARDCOPY_TRANSMIT,

SCREEN_DUMP.

Save/Recall Setup To preserve and restore front-panel settings:

PANEL_SETUP, *RCL, *RST, *SAV.

Status To obtain status information and set up service requests:

ALL_STATUS?, *CLS, CMR?, DDR?, *ESE, *ESR?, EXR?, INE, INR?, *IST?, *OPC, *PRE, *SRE, *STB?, URR?, *WAI.

Waveform Transfer To preserve and restore waveforms:

INSPECT?, STORE, TEMPLATE?, WAVEFORM, WAVEFORM_SETUP, WAVEFORM_TEXT.

Miscellaneous To control the calibration and test the instrument:

AUTO_CALIBRATE, *CAL?, *TST?.

To control the real-time clock:

DATE.

To control the built-in buzzer:

BUZZER.

To identify the instrument:

*IDN?, *OPT?.

COMMAND EXECUTION

Before attempting to execute a command or query, the oscilloscope scans it to verify its correctness and that sufficient information is given to perform the requested action. To protect the local user from changes in the oscilloscope's behavior which are beyond his control, the remote user must set the oscilloscope to the remote state to execute commands that affect the operation of the instrument as an oscilloscope. If such a command is received while the oscilloscope is operating in the local state, an execution permission error is generated and the execution of the command is denied. Vice versa, the local user cannnot interfere with the remote user because all front-panel controls are disabled while the oscilloscope is in the remote state.

Since interrogating the oscilloscope does not change its internal state, it may be queried at any time, independently of local or remote operation. There are only two exceptions to this rule: the queries *CAL? and *TST? both recalibrate the oscilloscope and are therefore executed in the remote state only.

Commands that only affect the remote behavior are executed independently of whether the oscilloscope is in the local or remote state. In this category are all commands that modify communication parameters (COMM_FORMAT, COMM_HEADER, COMM_HELP, COMM_ORDER, COMM_RS232), all commands affecting status information (*CLS, *ESE, INE, *OPC, *PRE, *SRE, *WAI), and the commands used to display messages on the screen to the local user (CALL HOST, KEY, MESSAGE).

In the description of each command, only exceptions to the rule that a command is executed only in the remote state and a query is executed in both the local and remote states are mentioned.

COMMAND NOTATION

The following notation is used in the description of the individual commands:

- < > Angular brackets enclose words that are used as placeholders. There are two types of placeholders: (1) the header path, (2) a data parameter of a command.
- A colon followed by an equals sign separates a placeholder from the description of the type and range of values that may be used in a command instead of the placeholder.
- { } Braces enclose a list of choices from which one must be selected.
- Square brackets enclose optional items.
- An ellipsis indicates that the items to the left and to the right of the ellipsis may be repeated zero or more times.

As an example, consider the syntax notation for the command to set the vertical input sensitivity:

> <channel>:VOLT_DIV <v_gain> <channel> := {C1, C2} $\langle v_{gain} \rangle := 5.0 \text{ mV to } 2.5 \text{ V}$

The first line shows the formal appearance of the command with <channel> denoting the placeholder for the header path, and <v_gain> denoting the placeholder for the data parameter specifying the desired vertical gain value. The second line indicates that either "C1" or "C2" must be chosen for the header path, and the third line explains that the actual vertical gain can be set to any value between 5 mV and 2.5 V.

STATUS

ALL_STATUS?, ALST?

Query

DESCRIPTION

The ALL_STATUS? query reads and clears the contents of all status registers: STB, ESR, INR, DDR, CMR, EXR, and URR except the MAV bit (bit 6) of the STB register. For an interpretation of the contents of each register, refer to the appropriate status register.

The ALL_STATUS? query is useful if a complete overview of the state of the instrument is required.

QUERY SYNTAX

ALl_STatus?

Response format

ALl STatus STB, <value>, ESR, <value>, INR, <value>, DDR, <value>, CMR <value>, EXR, <value>, URR, <value>

<value> := 0 to 65535

EXAMPLE (GPIB)

The following instruction reads the contents of all the status regis-

CMD\$="ALST?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message

ALST STB,000000,ESR,000052,INR,000005,DDR,000000,

EXR,000024,CMR,000004,URR,000000

RELATED COMMANDS

*CLS, CMR?, DDR?, *ESR?, EXR?, *STB?, URR?

ACQUISITION

ARM_ACQUISITION, ARM

Command

DESCRIPTION The ARM_ACQUISITION command enables the signal acquisi-

tion process by changing the acquisition state from "triggered" to

"ready".

COMMAND SYNTAX

ARM_acquisition

EXAMPLE

The following command enables signal acquisition.

CMD\$ = "ARM": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

STOP, *TRG, TRIG_MODE, WAIT

ACQUISITION

ATTENUATION, ATTN

Command/Query

DESCRIPTION

The ATTENUATION command selects the vertical attenuation

factor of the probe. Values of 1, 10, 100, 1000 or 10000 may be

specified.

The ATTENUATION? query returns the attenuation factor of the

specified channel.

COMMAND SYNTAX

<channel>:ATTeNuation <attenuation>

<channel> := {C1, C2, C3‡, C4‡}
<attenuation>:= {1, 10, 100, 1000, 10000}

QUERY SYNTAX

<channel>:ATTeNuation?

Response format

<channel>:ATTeNuation <attenuation>

EXAMPLE (GPIB)

The following command sets the attenuation factor of channel 1 to

100.

CMD\$="C1:ATTN 100": CALL IBWRT(SCOPE%,CMD\$)

MISCELLANEOUS

AUTO_CALIBRATE, ACAL

Command/Query

DESCRIPTION

The AUTO_CALIBRATE command is used to enable or disable automatic calibration of the instrument. At power-up, auto-calibration is turned ON, i.e. all input channels are periodically calibrated for the current gain, bandwidth and time-base settings.

The automatic calibration may be disabled by issuing the command ACAL OFF. Whenever it is convenient, a *CAL? query may be issued to fully calibrate the oscilloscope. When the oscilloscope is returned to local control, the periodic calibrations will be resumed.

The response to the AUTO_CALIBRATE? query indicates whether auto-calibration is enabled.

COMMAND SYNTAX

Auto CALibrate <state>

<state> := {ON, OFF}

QUERY SYNTAX

Auto_CALibrate?

Response Format

Auto_CALibrate <state>

EXAMPLE (GPIB)

The following instruction disables auto-calibration.

CMD\$="ACAL OFF": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

*CAL?

ACQUISITION

AUTO_SETUP, ASET

Command

DESCRIPTION

The AUTO SETUP attempts to display the input signal(s) by adjusting the vertical, time-base and trigger parameters. Auto-setup operates only on the channels whose traces are currently turned on. The only exception occurs when no traces are turned on, in which case AUTO_SETUP operates on all channels and turns on all of the traces.

If signals are detected on several channels, the lowest numbered channel with a signal determines the selection of the time base and trigger source.

If only one input channel is turned on, the time base will be adjusted for that channel.

COMMAND SYNTAX

Auto_SETup

EXAMPLE

The following command instructs the oscilloscope to perform an auto-setup.

CMD\$ = "ASET": CALL IBWRT(SCOPE%,CMD\$)

ACQUISITION

BANDWIDTH_LIMIT, BWL

Command/Query

DESCRIPTION The BANDWIDTH_LIMIT command enables or disables the

bandwidth limiting low pass filter.

The response to the BANDWIDTH_LIMIT? query indicates if the

bandwidth filter is on or off.

COMMAND SYNTAX BandWidth_Limit <mode>

<mode> := {ON, OFF}

QUERY SYNTAX BandWidth_Limit?

Response Format BandWidth_Limit <mode>

EXAMPLE The following command turns the bandwidth filter on.

CMD\$ = "BWL ON": CALL IBWRT(SCOPE%,CMD\$)

MISCELLANEOUS

BUZZER, BUZZ

Command

DESCRIPTION

The BUZZER command controls the built-in piezo-electric buzzer. This may be useful to attract the attention of a local operator in an interactive working application. The buzzer may either be activated for short beeps (about 400 msec long in BEEP mode) or continuously for a certain time interval selected by the user by turning the buzzer ON or OFF. A beep request which immediately follows another beep request will be held off for approximately 200 msec.

Note: This command is always accepted (local and remote).

COMMAND SYNTAX

BUZZer := {BEEP, ON, OFF}

EXAMPLE (GPIB)

Sending the following code will cause the oscilloscope to sound two short tones.

CMD\$ = "BUZZ BEEP; BUZZ BEEP";

CALL IBWRT(SCOPE%, CMD\$)

MISCELLANEOUS

*CAL?

Query

DESCRIPTION

The *CAL? query performs a complete internal calibration. This calibration sequence is the same as that which occurs at power-up. At the end of the calibration, the response indicates how the calibration terminated. When the calibration is finished, the instrument returns to the state it was in prior to the query.

Hardware failures are identified by a unique binary code in the returned <status> number (see Table 1). A "0" response indicates that no failures occurred.

Note: This query is only accepted in remote mode.

OUERY SYNTAX

*CAL?

Response Format

*CAL <diagnostics>

<diagnostics> := 0

calibration successful

BIT	BIT VALUE	DESCRIPTION
0	1	CH1 failure
1	2	CH2 failure
2	4	CH3 failure‡
3	8	CH4 failure‡
4	16	TDC failure
5	32	Trigger circuit failure
1		

Failures
Table 1

EXAMPLE (GPIB)

The following instruction forces a self-calibration.

CMD\$="*CAL?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%,RD\$): PRINT RD\$

Response message (if no failure)

*CAL 0

RELATED COMMANDS

AUTO_CALIBRATE

‡ 9424 only, reserved in the 9420/50

DISPLAY

CALL_HOST, CHST

Command/Query

DESCRIPTION

The CALL_HOST command allows the user to manually generate a service request (SRQ). Once the CALL HOST command has been received, the message "Call Host" will be displayed next to the lowest button (10) in the menu field (II). Pressing this button while in the root menu causes the User Request status Register (URR) and the URQ bit of the Event Status Register to be set. This can generate a SRQ in local mode provided that the service request mechanism has been enabled.

The response to the CALL_HOST? query indicates whether call host is enabled (on) or disabled (off).

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

Call HoST <state>

 $\langle state \rangle := \{ON, OFF\}$

QUERY SYNTAX

Call_HoST?

Response format

Call HoST <state>

EXAMPLE (GPIB)

After executing the following code an SRQ request will be generated whenever button 10 is pressed. It is assumed that SRQ

servicing has already been enabled.

CMD\$="CHST ON": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

URR?

STATUS

*CLS

Command

DESCRIPTION

The *CLS command clears all the status data registers.

Note: This command can be executed in both local and remote

modes.

COMMAND SYNTAX

*CLS

EXAMPLE (GPIB)

The following command causes all the status data registers to be

cleared.

CMD\$ = "*CLS": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

ALL_STATUS?, CMR?, DDR?, *ESR?, EXR?, *STB?, URR?

STATUS

CMR?

Query

DESCRIPTION

The CMR? query reads and clears the contents of the CoMmand error Register (CMR). The CMR register (Table 2) specifies the last syntax error type detected by the instrument.

QUERY SYNTAX

CMR?

Response format

CMR <value>

<value> := 1 to 13

EXAMPLE (GPIB)

The following instruction reads the contents of the CMR register.

CMD\$="CMR?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message

CMR 0

RELATED COMMANDS

ALL_STATUS?, *CLS

Value	Description
1	Unrecognized command/query header
2	Illegal header path
3	Illegal number
4	Illegal number suffix
5	Unrecognized keyword
6	String error
7	GET embedded in another message
10	Arbitrary data block expected
11	Non-digit character in byte count field of arbitrary data block
12	EOI detected during definite length data block transfer
13	Extra bytes detected during definite length data block transfer

Command Error Status Register Structure (CMR) Table 2

COMM_FORMAT, CFMT

Command/Query

DESCRIPTION

The COMM_FORMAT command selects the format which the oscilloscope will use to send waveform data. The available options allow (1) the block format, (2) the data type and (3) the encoding mode to be modified from the default settings.

Note: This command can be executed in both local and remote modes.

The COMM_FORMAT? query returns the currently selected waveform data format.

COMMAND SYNTAX

Comm ForMaT <block format>,<data type>,<encoding>

<block_format> := {DEF9, IND0, OFF}

<data_type> := {BYTE, WORD}

<encoding> := {BIN, HEX}

(GPIB uses both encoding forms, RS-232-C always uses HEX)

Initial settings (i.e. after power on) are:

DEF9, WORD, BIN for GPIB

DEF9, WORD, HEX for RS-232-C

QUERY SYNTAX

Comm_ForMaT?

Response Format

Comm_ForMaT <block_format>,<data_type>,<encoding>

EXAMPLE (GPIB)

The following code redefines the transmission format of waveform data. The data will be transmitted as a block of indefinite length. Data will be coded in binary and represented as 8-bit integers.

CMD\$="CFMT IND0,BYTE,BIN" CALL IBWRT(SCOPE%,CMD\$)

would be sent as:

EXPLANATION

BLOCK FORMAT

DEF9: Uses the IEEE 488.2 definite length arbitrary block response data format. The digit 9 indicates that the byte count consists of 9 digits. The data block directly follows the byte count field.

For example, a data block consisting of 3 data bytes

WF DAT1,#900000003<DAB><DAB><DAB> where <DAB> represents an 8-bit binary data byte.

IND0: Uses the IEEE 488.2 indefinite length arbitrary block response data format.

A <NL^END> (new line with EOI) signifies that block transmission has ended.

The same data bytes as above would be sent as:

WF DAT1,#0<DAB><DAB><NL^END>

OFF: Same as IND0. In addition, the data block type identifier and the leading #0 of the indefinite length block will be suppressed. The data presented above would be sent as:

WF <DAB><DAB><NL^END>

Note: The format OFF does not conform to the IEEE 488.2 standard and is only provided for special applications where the absolute minimum of data transfer may be important.

DATA TYPE

BYTE: Transmits the waveform data as 8-bit integers (1 byte).

WORD: Transmits the waveform data as 16-bit integers (2 bytes).

ENCODING

BIN: Binary encoding (GPIB only)

HEX: Hexadecimal encoding (bytes are converted to 2 hexadecimal ASCII digits (0, ... 9, A, ... F))

RELATED COMMANDS WAVEFORM?

COMM_HEADER, CHDR

Command/Query

DESCRIPTION

The COMM_HEADER command controls the way the oscilloscope will format responses to queries. The instrument provides three response formats: (1) LONG format, i.e. responses start with the long form of the header word; (2) SHORT format, i.e. responses start with the short form of the header word; (3) OFF, i.e. headers are omitted from the response and suffix units in numbers are suppressed. Until the user requests otherwise, the SHORT response format is used.

This command does not affect the interpretation of messages sent to the oscilloscope. Headers may be sent in their long or short form regardless of the COMM_HEADER setting.

Querying the vertical sensitivity of Channel 1 may result in one of the following responses:

COMM_HEADER	RESPONSE
LONG	CHANNEL_1:VOLT_DIV 200E-3 V
SHORT	C1:VDIV 200E-3 V
OFF	200E-3

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

Comm_HeaDeR <mode>

<mode> := {SHORT, LONG, OFF}

Note: The default mode, i.e. the mode just after power on, is SHORT.

QUERY SYNTAX

Comm_HeaDeR?

Response Format

Comm_HeaDeR <mode>

EXAMPLE (GPIB)

The following code sets the response header format to short.

CMD\$ = "CHDR SHORT"; CALL IBWRT(SCOPE%,CMD\$)

COMM_HELP, CHLP

Command/Query

DESCRIPTION

The COMM_HELP command enables the help diagnostics utility to assist remote program debugging. When turned on, this utility displays all message transactions occurring between the controller and the oscilloscope on a terminal, printer or similar recording device connected to the RS-232-C port. Errors detected by the instrument can be directly viewed.

Note: This command can be executed in both local and remote modes.

The COMM_HELP? query indicates if the diagnostics utility has been enabled.

COMMAND SYNTAX

Comm_HeLP <target>

<target> := {RS, OFF}

The initial <target>, (i.e. after power on) is OFF.

QUERY SYNTAX

Comm_HeLP?

Response Format

Comm_HeLP <target>

EXAMPLE (GPIB)

The following code turns on the remote control diagnostics utility.

CMD\$="CHLP RS"; CALL IBWRT(SCOPE%,CMD\$)

COMM_ORDER, CORD

Command/Query

DESCRIPTION

The COMM_ORDER command controls the byte order of waveform data transfers. Waveform data may be sent with the most significant byte (MSB) or the least significant byte (LSB) in the first position. The default mode is the MSB first.

COMM_ORDER applies equally to the waveform's descriptor and time blocks. In the descriptor some values are 16 bits long ("word"), 32 bits long ("long" or "float"), or 64 bits long ("double"). In the time block all values are floating values, i.e. 32 bits long. When "COMM_ORDER HI" is selected the most significant byte is sent first. When "COMM_ORDER LO" is specified the least significant byte is sent first.

The COMM_ORDER? query returns the byte transmission order currently in use.

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

Comm_ORDer <mode>

 $< mode > := \{HI, LO\}$

Note: The initial mode, i.e. the mode after power on, is HI.

QUERY SYNTAX

Comm_ORDer?

Response Format

Comm_ORDer <mode>

EXAMPLE

The order of transmission of waveform data depends on the data

type. Table 3 illustrates the different possibilities.

System Commands 5

- 4	
44	ь
	٦
	- 2

Туре	CORD HI	CORD LO
Word	<msb><lsb></lsb></msb>	<lsb><msb></msb></lsb>
Long/float	<msb><byte 2=""><byte 3=""><lsb></lsb></byte></byte></msb>	<lsb><byte 3=""><byte 2=""><msb></msb></byte></byte></lsb>
Double	<msb><byte 2=""> <byte 7=""><lsb></lsb></byte></byte></msb>	<lsb><byte 7=""> <byte 2=""><msb></msb></byte></byte></lsb>

Waveform Data Transmission Order

Table 3

RELATED COMMANDS

WAVEFORM?

COMM RS232, CORS

Command/Query

DESCRIPTION

The command COMM_RS232 sets the parameters of the RS-232-C port for remote control.

The COMM_RS232? query reports the settings of the parameters.

Note: This command is ONLY valid if the oscilloscope is being remotely controlled via the RS-232-C port.

The parameters are:

- a. DUPLEX behavior mode.
- b. End Input character. When received by the oscilloscope, this character will be interpreted as the END-of-a-command message marker. The commands received will be parsed and executed.
- c. End Output string. The oscilloscope will add this string at the end of a response message. When the host computer receives this string, it knows that the oscilloscope has completed its response.
- d. Line Length. This parameter defines the maximum number of characters that will be sent to the host in a single line. Remaining characters of the response will be output in separate additional lines. This parameter is only applicable if a line separator has been selected.
- e. Line Separator. This parameter is used to select the line splitting mechanism and to define the characters used to split the oscilloscope response messages into many lines. Possible line separators are: CR, LF, CRLF. A <CR>, a <LF> or a <CR> followed by a <LF> will be sent to the host computer after line_length> characters.
- f. SRQ string. This string is sent each time the oscilloscope wants to signal an SRQ to the host computer.

Note: Some parameters of this command require ASCII strings as actual arguments. In order to facilitate the embedding of non-printable characters into such strings, escape sequences may be

used. the back-slash character ('\') is used as an escape character. The following escape sequences are recognized:

"\a": Bell character,

"\b": Back space character,

"\e": Escape character,

"\n": Line feed character,

"\r": Carriage return character,

"\t": Horizontal tab character,

"\\": The back-slash character itself

"\ddd": ddd represents one to three decimal digit characters giving the code value of the corresponding ASCII character. This allows any ASCII code in the range 1 to 127 to be inserted.

Before using the string, the oscilloscope will replace the escape sequence by the corresponding ASCII character.

For example, the escape sequences "\r", "\13" and "\013" are all replaced by the single ASCII character <Carriage Return>.

Notation

DUPLEX duplex El End input character

EO End output string LL Line length

LS Line separator SRQ SRQ Service request

COMMAND SYNTAX

COmm_RS232 DUPLEX,<duplex>,EI,<ei_char>, EO,'<eo_string>',LL,<line_length>,LS,<Line_sep>, SRQ,'<srq_string>'

<duplex> := FULL (only full duplex is currently implemented)

 $\langle ei_char \rangle := 1 \text{ to } 126$ (default: $13 = \langle CR \rangle$)

<eo_string> := A non-empty ASCII string of up to 20 characters.

(default: "\n\r")

line_length> := 40 to 1024 (default: 256)

line_sep> := {OFF, CR, LF, CRLF} (default: OFF)

<srq_string> := An ASCII string which may be empty.

(default: empty string)

5 System Commands

QUERY SYNTAX

COmm_RS232?

Response Format

COmm_RS232 DUPLEX,<duplex>,EI,<ei_char>,

EO, "<eo_string>",

LL,<line_length>,LS,<line_sep>,SRQ,"<srq_string>"

EXAMPLE

After executing the command

COMM_RS232 EI,3,EO,"\R\NEND\R\N"

the oscilloscope will assume that it has received a complete message each time the <ETX> (decimal value 3) is detected. Response messages will be terminated by sending the character sequence

"<CR><LF>END<CR><LF>".

ACQUISITION

COUPLING, CPL

Command/Query

DESCRIPTION

The COUPLING command selects the coupling mode of the speci-

fied input channel.

The COUPLING? query returns the coupling mode of the speci-

fied channel.

COMMAND SYNTAX

<channel>:CouPLing <coupling>

<channel> := {C1, C2, C3‡, C4‡}

<coupling $> := \{A1M, D1M, D50, GND\}$

QUERY SYNTAX

<channel>:CouPLing?

Response format

<channel>:CouPLing <coupling>

EXAMPLE GPIB)

The following command sets the coupling of Channel 2 to

50 Ω DC.

CMD\$="C2:CPL D50": CALL IBWRT(SCOPE%,CMD\$)

CURSOR

CURSOR_MEASURE, CRMS

Command/Query

DESCRIPTION

The CURSOR_MEASURE command specifies the type of cursor to be displayed.

The CURSOR_MEASURE? query indicates which cursors are currently displayed.

Notation

HABS HREL Horizontal relative Horizontal absolute **VABS** Vertical absolute VREL Vertical relative **PARAM Parameters** OFF Cursors off

Note: The PARAM mode is turned OFF when the XY mode is ON.

COMMAND SYNTAX

CuRsor_MeaSure <mode>

<mode> := {HABS, VABS, HREL, VREL, PARAM, OFF}

QUERY SYNTAX

CuRsor_MeaSure?

Response Format

CuRsor MeaSure <mode>

EXAMPLE (GPIB)

The following command switches on the vertical relative cursors.

CMD\$="CRMS VREL": CALL IBWRT(SCOPE%,CMD\$)

The following command determines which cursor is currently turned on.

CMDS\$="CRMS?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RD\$): PRINT RD\$

Example of response message

CRMS OFF

CURSOR

CURSOR_SET, CRST

Command/Query

DESCRIPTION

The CURSOR_SET command allows the user to position any one of the eight independent cursors at a given screen location. The positions of the cursors can be modified or queried even if the required cursor is not currently displayed on the screen.

When setting a cursor position, a trace must be specified, relative to which the cursor will be positioned.

The CURSOR_SET? query indicates the current position of the cursor(s). The values returned depend on the grid type selected.

Note 1: When the oscilloscope is in the dual grid mode, traces are assigned to either the upper grid (EA, MC, FE, C1, C3‡) or lower grid (EB, MD, FF, C2, C4‡). The trace specified determines whether a vertical cursor will be placed relative to the upper or lower grid.

In quad grid mode‡ each channel is permanently assigned to its respective grid with C1 at the top and C4 at the bottom. All other traces may be re-positioned anywhere on the screen using the vertical position control.

Note 2: If the parameter display is turned on, the parameters of the specified trace will be shown unless the newly chosen trace is not displayed or has been acquired in sequence mode (these conditions will produce an environment error, see Table 6, page 82). To only change the trace without repositioning the cursors, the CURSOR_SET command may be given with no argument, (e.g. EB: CRST).

Notation

HABS Horizontal absolute
VABS Vertical absolute
HREF Horizontal reference
VREF Vertical reference
PREF Parameter reference
PDIF Parameter difference

COMMAND SYNTAX

<trace>:CuRsor_SeT <cursor>,<position>[<cursor>,<position>, ...<cursor>,<position>]

:= {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡} <trace> := {HABS, VABS, HREF, HDIF, VREF, VDIF, <cursor> PREF, PDIF}

<position> := 0 to 10 DIV (horizontal) -13 to 13 DIV (vertical)

Note 1: The suffix DIV is optional.

Note 2: Parameters are grouped in pairs. The first parameter specifies the cursor to be modified and the second one indicates its new value. Parameters may be grouped in any order and may be restricted to those items to be changed.

QUERY SYNTAX

<trace>:CuRsor_SeT? [<cursor>,...<cursor>]

<cursor>:= {HABS, VABS, HREF, HDIF, VREF, VDIF, PREF, PDIF, ALL}

Response Format

<trace>:CuRsor_SeT <cursor>,<position>[<cursor>,<position>,

...<cursor>,<position>]

If <cursor> is not specified, ALL will be assumed. If the position of a cursor cannot be determined in a particular situation, its position will be indicated as UNDEF.

EXAMPLE (GPIB)

The following command positions the VREF and VDIF cursors at +3 DIV and -7 DIV respectively, using Function E as a reference.

CMD\$="FE:CRST VREF,3DIV,VDIF,-7DIV"

CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

CURSOR VALUE?, PARAMETER_VALUE?

CURSOR

CURSOR VALUE?, CRVA?

Query

DESCRIPTION

The CURSOR_VALUE? query returns the values measured by the specified cursors for a given trace. (The PARAME-TER_VALUE? query is used to obtain measured waveform parameter values.)

Notation

HABS Horizontal absolute HREL Horizontal relative VABS Vertical absolute VREL Vertical relative

QUERY SYNTAX

<trace>:CuRsor_VAlue? [<mode>,...<mode>]

<trace> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡} <mode> := {HABS, VABS, HREL, VREL, ALL}

Response Format

<trace>:CuRsor_VAlue? <mode>[,<hor_value>],<ver value>[, ...,<mode>[,<hor_value>],<ver_value>]

For horizontal cursors, both horizontal as well as vertical values are given, whereas for vertical cursors only vertical values are given.

Note: If <mode> is not specified or equals ALL, all the measured cursor values for the specified trace are returned. If the value of a cursor could not be determined in the current environment, the value UNDEF will be returned.

EXAMPLE (GPIB)

The following query reads the measured absolute horizontal value of the cross-hair cursor (HABS) on Channel 2.

CMD\$="C2:CRVA? HABS": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message

"C2:CVRA HABS,34.2 US,244 MV"

RELATED COMMANDS

CURSOR SET

‡ 9424 only

MISCELLANEOUS

DATE

Command/Query

DESCRIPTION

The DATE command changes the date/time of the oscilloscope's internal real time clock.

The DATE? query returns the current date/time setting.

COMMAND SYNTAX

DATE <day>,<month>,<year>,<hour>,<minute>,<second>

< day> := 1 to 31

<month> := {JAN, FEB, MAR, APR, MAY, JUN, JUL,

AUG, SEP, OCT, NOV, DEC}

<year> := 1987 to 2500
<hour> := 0 to 23

<minute> := 0 to 59

<second> := 0 to 59

Note: It is not always necessary to specify all the DATE parameters. Only the parameters up to and including the parameter to be changed need to be specified, i.e. to change the "year" setting specify day, month and year together with the required settings. The time settings will remain unchanged. To change the "second" setting all the DATE parameters must be specified with the required settings.

QUERY SYNTAX

DATE?

Response format

DATE <day>,<month>,<year>,<hour>,<minute>,<second>

EXAMPLE (GPIB)

This example will change the date to October 1, 88 and the time to

1:21:16 p.m. (13:21:16 in 24 hour notation).

CMD\$="DATE 1,OCT,1988,13,21,16" CALL IBWRT(SCOPE%,CMD\$) **STATUS**

DDR?

Query

DESCRIPTION

The DDR? query reads and clears the contents of the Device Dependent or device specific error Register (DDR). In the case of a hardware failure, the DDR register specifies the origin of the failure. Refer to Table 4, page 66, for further details.

QUERY SYNTAX

DDR?

Response format

DDR <value>

<value> := 0 to 65535

EXAMPLE (GPIB)

The following instruction reads the contents of the DDR register.

CMD\$="DDR?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message

DDR 0

RELATED COMMANDS

ALL_STATUS?, *CLS

Bit	Bit Value	Description
1514		0 Reserved
13	8192	1 time-base hardware fallure is detected
12	4096	1 a trigger hardware fallure is detected
11	2048	1 a Channel 4‡ hardware fallure is detected.
10	1024	1 a Channel 3‡ hardware failure is detected.
9	512	1 a Channel 2 hardware failure is detected
8	256	1 a Channel 1 hardware fallure Is detected
74		0 Reserved
3	8	1 a Channel 4‡ overload condition is detected
2	4	1 a Channel 3‡ overload condition is detected1
1	2	1 a Channel 2 overload condition is detected
0	1	1 a Channel 1 overload condition is detected

Device Specific Register Structure (DDR) Table 4

^{‡ 9424} only, reserved in 9420/50

FUNCTION

DEFINE, DEF

Command/Query

Standard Oscilloscopes

DESCRIPTION

The DEFINE command specifies the mathematical expression to be evaluated by a function.

Notation			
MAXPTS SWEEPS	maximum nun maximum nun		
EQN	equation	AVGS	average summed
C1	Channel 1	C2	Channel 2
C3	Channel 3‡	C4	Channel 4‡

COMMAND SYNTAX

<function>:DEFine EQN,'<equation>',MAXPTS,<max_points>,
SWEEPS,<max sweeps>

 $< function > := \{MC^{\ddagger}, MD^{\ddagger}, FE, FF\}$

<source> := {C1, C2, C3‡, C4‡}

 $< max_points > := 50 to 50000 on 1-2-5 scale$

<max_sweeps> := 1 to 1000

Note 1: Parameters are grouped in pairs. The first one names the variable to be modified and the second one gives the new value to be assigned. Pairs may be given in any order and may be restricted to the variables to be changed.

Note 2: The pair SWEEPS, <max_sweeps> applies only when averaging (AVGS) has been chosen. Otherwise it is ignored.

QUERY SYNTAX

<function>:DEFine?

Response format

<function>:DEFine EQN,'<equation>',MAXPTS,<max_points>
[,SWEEPS,<max_sweeps>]

EXAMPLE (GPIB)

The following command defines Function E (FE) to compute the summed average of Channel 1 using 5000 points over 200 sweeps.

CMD\$="FE:DEF EQN,'AVGS(C1)', MAXPTS, 5000,SWEEPS,200" CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

FUNCTION_RESET, FUNCTION_STATE‡, INR?

FUNCTION

DEFINE, DEF

Command/Query

Oscilloscopes fitted with the WP01 Option

DESCRIPTION

An oscilloscope fitted with the Waveform Processing option (WP01) accepts additional forms of the DEFINE command:

Processin	Processing Notation		
ABS	Absolute Value		
AVGC	Continuous Average		
AVGS	Summed Average		
DERI	Derivative		
EXP	Exponential (power of e)		
EXP10	Exponential (power of 10)		
EXTR	Extrema		
FLOOR	Floor (Extrema only)		
HRES	High Resolution Filter		
INTG	Integral		
LOG10	Logarithm base 10		
LN	Logarithm base e		
ROOF	Roof (Extrema only)		
SQR	Square		
SQRT	Square Root		
+	Identity or Add		
-	Negation or Subtract		
*	Multiply		
/	Ratio		
1/	Reciprocal		

Key words

BITS Resolution enhancement, bits (High Resolution only)

DITHER Dither (Summed Average only)

MAXPTS Maximum number of points

REJECT Reject overflow/underflow (Summed Average only)

SWEEPS Maximum number of sweeps (Average and Extrema only)

WEIGHT Weight (Continuous Average only)

COMMAND SYNTAX

<function>:DEFine EQN,'<equation>', MAXPTS,<max_points>, SWEEPS,<max sweeps>, DITHER,<off_on>, REJECT, <off_on>, WEIGHT, <weight>, BITS, <bits> <function> := {MC\$, MD\$, FE, FF} <equation> := AVGS(<source>) Summed Average Continuous Average <equation> := AVGC(<source>) Identity <equation> := <paren_source_expr> <equation> := +<paren_source_expr> Identity <equation> := -<paren_source_expr> Negation <equation> := 1/<paren_source_expr> Reciprocal <equation> := <paren_source_expr> + <source> Addition <equation> := <paren_source_expr> - <source> Subtraction <equation> := <paren_source_expr> * <source> Multiplication <equation> := <paren_source_expr> / <source> Ratio Extrema (R+F) <equation> := EXTR(<source>)

```
<equation> := FLOOR(EXTR(<source>)) Floor
<equation> := ROOF(EXTR(<source>))
                                        Roof
<equation> := SQR(<source_expr>)
                                        Square
<equation> := SQRT(<source_expr>)
                                        Square Root
<equation> := LN(<source_expr>)
                                        Logarithm base e
<equation> := LOG10(<source_expr>)
                                        Logarithm base 10
<equation> := EXP(<source_expr>)
                                        Power of e
<equation> := EXP10(<source_expr>)
                                        Power of 10
<equation> := INTG(<source_expr>)
                                        Integral
<equation> := DERI(<source_expr>)
                                        Derivative
<equation> := ABS(<source_expr>)
                                        Absolute Value
<equation> := HRES(<source>)
                                        High Resolution
<paren_source_expr> := (<source_expr>)
<paren_source_expr> := <source>
<source_expr> := <multiplier> * <source> {+, -} <addend>
<source_expr> := <multiplier> * <source>
<source_expr> := <source> {+, -} <addend>
<source_expr> := <source>
<multiplier> := 0.001e-33 to 999.999e33
< addend > := -999.999e33 to 999.999e33
<source> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}
< max points > := 40 to 50000
< max_sweeps > := 1 to 1000000
< off_on > := {OFF, ON}
<weight> := {1, 3, 7, 15, 31, 63, 127}
<br/><bits> := {0.5, 1.0, 1.5, 2.0, 2.5, 3.0}
Note: Space (blank) characters inside equations are optional.
```

QUERY SYNTAX

<function>:DEFINE?

Response format

<function>:DEFine EQN,'<equation>', MAXPTS,<max_points>,

SWEEPS,<max_sweeps>, DITHER,<off_on>,

REJECT,<off_on>, WEIGHT,<weight>, BITS,<bits>

EXAMPLE (GPIB):

The following command defines Function E to compute the prod-

uct of (Channel 1 multiplied by 2.1 and augmented by 3.3) and

Channel 2, using a maximum of 10000 input points:

CMD\$="FE:DEF EQN,'(2.1*C1+3.3)*C2', MAXPTS,10000"

CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

FUNCTION_RESET, FUNCTION_STATE‡, INR?

FUNCTION

DEFINE, DEF

Command/Query

Oscilloscopes fitted with the WP02 Option

DESCRIPTION

An oscilloscope fitted with the FFT option (WP02) accepts additional forms of the DEFINE command.

Notation	
WINDOW FFT REAL IMAG MAG PHASE	FFT window function Fast Fourier Transform (complex result) Real part of complex result Imaginary part of complex result Magnitude of complex result Phase angle (degrees) of complex result
PS PSD AVGP RECT HANN HAMM FLTP BLHA DCSUP	Power Spectrum Power Density Power Average Rectangular window von Hann window Hamming window Flat Top window Blackman-Harris window DC component suppression

```
COMMAND SYNTAX (FFT)
                          < function >: DEFine EQN,' < equation >',
```

MAXPTS, < max_points > ,WINDOW, < window_type > ,

DCSUP, < off_on >

<function> := {MC\pm, MD\pm, FE, FF}

<equation> := FFT(<source_expr>)

<equation> := REAL(FFT(<source expr>))

<equation> := IMAG(FFT(<source_expr>))

<equation> := MAG(FFT(<source_expr>))

<equation> := PHASE(FFT(<source_expr>))

<equation> := PS(FFT(<source_expr>))

<equation> := PSD(FFT(<source_expr>))

<source_expr> := <multiplier> * <source> {+, -} <addend>

<source_expr> := <multiplier> * <source>

^{‡ 9424} only

<source_expr> := <source> {+, -} <addend>

<source expr> := <source>

<multiplier> := 0.001e-33 to 999.999e33
<addend> := -999.999e33 to 999.999e33

<source> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}
<window_type> := {RECT, HANN, HAMM, FLTP, BLHA}

 $\langle off on \rangle := \{OFF, ON\}$

Note: The source waveform must be a time domain signal.

QUERY SYNTAX

<function>:DEFine?

Response Format

<function>:DEFine EQN,'<equation>',MAXPTS,<max_points>,
WINDOW,<window_type>,DCSUP,<off_on>

EXAMPLE (GPIB)

The following command defines Function E to compute the Power Spectrum of the FFT of Channel 1. Prior to FFT computation, Channel 1 is multiplied by 1.018 and 0.055 (units of Channel 1, i.e. Volts) is added. A maximum of 1000 points will be used for the input. The window function is Rectangular. The DC component of the input is not suppressed.

CMD\$="FE:DEF EQN,'PS(FFT(1.018*C1 + 0.055))', MAXPTS,1000,WINDOW,RECT,DCSUP,OFF"

CALL IBWRT(SCOPE%,CMD\$)

COMMAND SYNTAX

(FFT Power Average)

< function >: DEFine EQN,' < equation >',

SWEEPS, < max sweeps >

<equation> := MAG(AVGP(<source>))
<equation> := PS(AVGP(<source>))
<equation> := PSD(AVGP(<source>))
<source> := {MC‡, MD‡, FE, FF}

< max sweeps > := 1 to 50000

Note: The source waveform must be another function defined as a Fourier transform.

QUERY SYNTAX

<function>:DEFine?

Response Format

<function>:DEFine EQN,'<equation>',SWEEPS,<max_sweeps>

‡ 9424 only

EXAMPLE (GPIB)

The following command defines Function F to compute the Power

Spectrum of the Power Average of the FFT being computed by the Function E, over a maximum of 244 sweeps.

CMD\$="FF:DEF EQN,'PS(AVGP(FE))',SWEEPS,244"

CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

FUNCTION_RESET, FUNCTION_STATE‡, INR?

DISPLAY, DISP

Command/Query

DESCRIPTION

The DISPLAY command controls the display screen of the oscilloscope. When the user is remotely controlling the oscilloscope and does not need to use the display, it may be useful to switch off the display via the DISPLAY OFF command. This improves instrument response time since the waveform graphic generation procedure is suppressed.

The response to the DISPLAY? query indicates the display state of the oscilloscope.

Note: When the display has been set to OFF, the real time clock and the message field are updated. However, the waveforms and associated texts remain unchanged.

COMMAND SYNTAX

DISPlay <state>

<state> := {ON, OFF}

QUERY SYNTAX

DISPlay?

Response Format

DISPlay <state>

EXAMPLE (GPIB)

The following instruction turns off the display generation.

CMD\$="DISP OFF": CALL IBWRT(SCOPE%,CMD\$)

DUAL_ZOOM, DZOM

Command/Query

DESCRIPTION

By setting DUAL ZOOM ON, the horizontal magnification and positioning controls apply to all expanded traces simultaneously. This command is useful if the contents of all expanded traces are

to be examined at the same time.

The DUAL_ZOOM? query indicates whether multiple zoom is en-

abled or not.

Note: This command has the same effect as MULTI_ZOOM.

COMMAND SYNTAX

Dual ZOoM <mode>

 $< mode > := \{ON, OFF\}$

QUERY SYNTAX

Dual_ZOoM?

Response format

Dual_ZOoM <mode>

EXAMPLE (GPIB)

The following example turns dual zoom on.

CMD\$="DZOM ON": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

HOR_MAGNIFY, HOR_POSITION, MULTI_ZOOM, ZOOM

STATUS

*ESE

Command/Query

DESCRIPTION

The *ESE command sets the standard Event Status Enable register (ESE). This command allows one or more events in the ESR register to be reflected in the ESB summary message bit (bit 5) of the STB register. For an overview of the ESB defined events refer to the ESR table (Table 5, page 80).

The *ESE? query reads the contents of the ESE register.

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

*ESE <value>

 $\langle value \rangle := 0$ to 255

QUERY SYNTAX

*ESE?

Response format

*ESE <value>

EXAMPLE (GPIB)

The following command allows the ESB bit to be set if a user request (URQ bit 6, i.e. decimal 64) and/or a device dependent error (DDE bit 3, i.e. decimal 8) occurs. Summing these values

yields the ESE register mask 64+8=72.

CMD\$="*ESE 72": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

*ESR?

STATUS

*ESR?

Query

DESCRIPTION

The *ESR? query reads and clears the contents of the Event Status Register (ESR). The response represents the sum of the binary values of the register bits 0 to 7. Refer to Table 5, page 80 for an overview of the ESR register structure.

QUERY SYNTAX

*ESR?

Response format

*ESR <value>

<value> := 0 to 255

EXAMPLE (GPIB)

The following instruction reads and clears the contents of the ESR

register.

CMD\$="*ESR?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%,RSP\$): PRINT RSP\$

Response message

*ESR 0

RELATED COMMANDS

ALL_STATUS?, *CLS, *ESE

Bit	Bit Value	Bit Name	Description	Note
158			0 Reserved by IEEE 488.2	
7	128	PON	1 a Power off-to-ON transition has occurred	(1)
- 6	64	URQ	1 a User ReQuest has been issued	(2)
5	32	СМЕ	1 a CoMmand parser Error has been found	(3)
4	16	EXE	1 an Execution Error has been detected	(4)
3	8	DDE	1 a Device Specific Error has occurred	(5)
2	4	QYE	1 a QueRy Error has occurred	(6)
1	2	RQC	0 The instrument never requests bus control	(7)
0	1	OPC	0 The OPeration Complete bit is not used	(8)

Standard Event Status Register (ESR)

Table 5

Notes:

- (1) The Power On (PON) bit is always turned on (1) when the unit is powered up.
- (2) The User Request (URQ) bit is set true (1) when a soft key is pressed. An associated register URR identifies which key was selected. For further details refer to the URR? query.
- (3) The CoMmand parser Error bit (CME) is set true (1) whenever a command syntax error is detected. The CME bit has an associated CoMmand parser Register (CMR) which specifies the error code. Refer to the query CMR? for further details.
- (4) The EXecution Error bit (EXE) is set true (1) when a command cannot be executed due to some device condition (e.g. oscilloscope in local state) or a semantic error. The EXE bit has an associated Execution Error Register (EXR) which specifies the error code. Refer to query EXR? for further details.
- (5) The Device specific Error (DDE) is set true (1) whenever a hardware failure has occurred at power-up or execution time such as a channel overload condition, a trigger or a time-base circuit defect. The origin of the failure may be localized via the DDR? or the self test *TST? query.
- (6) The Query Error bit (QYE) is set true (1) whenever (a) an attempt is being made to read data from the Output Queue when no output is either present or pending, (b) data in the Output Queue has been lost, (c) both output and input buffers are full (deadlock state), (d) an attempt is made by the controller to read before having sent an <END>, (e) a command is received before the response to the previous query was read (output buffer flushed).
- (7) The ReQuest Control bit (RQC) is always false (0) since the oscilloscope has no GPIB controlling capability.
- (8) The OPeration Complete bit (OPC) is set true (1) whenever *OPC has been received since commands and queries are strictly executed in sequential order. The oscilloscope starts processing a command only once the previous command has been entirely executed.

STATUS

EXR?

Query

DESCRIPTION

The EXR? query reads and clears the contents of the EXecution error Register (EXR). The EXR register specifies the type of the last error detected during execution. Refer to Table 6, page 82 for further details.

QUERY SYNTAX

EXR?

Response format

EXR <value>

<value> := 21 to 35

EXAMPLE (GPIB)

The following instruction reads the contents of the EXR register.

CMD\$="*EXR?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message (if no fault)

EXR 0

RELATED COMMANDS

ALL_STATUS?, *CLS

Value	Description	
21	Permission error. The command cannot be executed in local mode.	
22	Environment error. The instrument is not configured to correctly process a command. For instance, the osciloscope cannot be set to RiS at a slow time base.	
23	Option error. The command applies to an option which has not been installed.	
24	Unresolved parsing error.	
25	Parameter error. Too many parameters specified.	
26	Non-implemented command.	
30	Hex data error. A non-hexadecimal character has been detected in a hex data block.	
31	Waveform error. The amount of data received does not correspond to descriptor indicators.	
32	Waveform descriptor error. An invalid waveform descriptor has been detected.	
33	Waveform time error. Invalid RIS or TRIG time data has been detected.	
34	Waveform data error. Invalld waveform data have been detected.	
35	Panel setup error. An invalid panel setup data block has been detected.	

Execution Error Status Register Structure (EXR) Table 6

FUNCTION

FUNCTION_RESET, FRST

Command

DESCRIPTION

The FUNCTION_RESET command resets a waveform processing function. The number of sweeps will be reset to zero and the proc-

ess restarted.

COMMAND SYNTAX

 $<\!function\!>:\!Function_ReSeT$

EXAMPLE (GPIB)

<function> := {MC‡, MD‡, FE, FF}

Assuming that Function E (FE) has been defined as the summed average of Channel 1, the following example will restart the aver-

aging process.

CMD\$="FE:FRST": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

DEFINE, INR?

FUNCTION

FUNCTION_STATE, FSTA‡

Command/Ouerv

DESCRIPTION

The FUNCTION_STATE command allows the user to control or enquire how Functions C, D, E and F are being used. The four waveform processing functions may assume up to three different states:

static memory of a waveform (no further automatic pro-**MEM** cessing occurs)

expansion of another waveform (updated as the source ZOOM changes)

a mathematical function of one or two other waveforms **FUNC** (updated if one of the sources change)

The two Functions C and D may assume all three states whereas E and F may assume only the states MEM and FUNC. The setup information needed to execute expansions or mathematical waveform processing is memorized separately by the oscilloscope for each function. When the state of a function is changed, the last setup information associated with the new state will be reactivated.

There are three other commands which may cause a state transition. The command ZOOM applied to Functions C or D will automatically switch them into zoom state. The commands STORE (storage from internal waveform) and WAVEFORM (storage from external waveform) applied to any one of the Functions C, D, E or F will automatically switch them into the memory state. There is never an automatic transition into the function state. The command FUNCTION_STATE must be used.

Initially Functions C and D are set to the memory state and Functions E and F are set to the function state.

The query FUNCTION STATE returns the current state of a waveform processing function.

COMMAND SYNTAX

<function>:Function_STAte <state> <function> := {MC, MD, FE, FF} <state> := {FUNC, MEM, ZOOM}

‡ 9424 only

QUERY SYNTAX

<function>:Function_STAte?

Response format

<function>:Function_STAte <state>

EXAMPLE (GPIB)

The following example switches the internal function memory C into the mathematical waveform processing state thereby re-estab-

lishing the last valid waveform processing definition.

CMD\$="MC:FSTA FUNC": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

DEFINE, STORE, WAVEFORM, ZOOM

GRID

Command/Query

DESCRIPTION

The GRID command specifies whether the grid should be displayed in single, dual or quad‡ mode.

In single grid mode all the traces are displayed on a single grid.

In dual grid mode the screen is split into two distinct grids to separate the traces. In the 9420/50, Channel 1 is always displayed in the upper grid and Channel 2 in the lower grid. In the 9424, Channels 1 and 2 are always displayed in the upper grid and Channels 3 and 4 in the lower grid. All other waveforms can be vertically positioned anywhere.

In quad grid mode‡ Channel 1 is always displayed in the upper grid, Channel 2 in the second grid, etc. All other waveforms can be vertically positioned anywhere.

The GRID? query returns the grid mode currently in use.

COMMAND SYNTAX

GRID <grid>

<grid> := {SINGLE, DUAL, QUAD‡}

QUERY SYNTAX

GRID?

Response Format

GRID <grid>

EXAMPLE (GPIB)

The following command sets the screen display to dual grid mode.

CMD\$="GRID DUAL": CALL IBWRT(SCOPE%,CMD\$)

HARD COPY

HARDCOPY SETUP, HCSU

Command/Query

DESCRIPTION

The HARDCOPY_SETUP command configures the instrument's hard copy driver. The command enables the user to specify the device type, transmission mode, plot size etc. of the hard-copy unit connected to the oscilloscope.

The command allows one or more individual settings to be changed by specifying the appropriate keyword(s) together with the new value(s). For instance, to select the Graphtec FP5301 plotter with normal speed, the command may be restricted to:

HCSU DEV,FP5301,SPEED,N

Notation			
DEV	device	PORT	port
SPEED	plot speed	DENS	print density
PENS	plot pens	PFEED	page feed
PSIZE	paper size	GRID	grid square
LLX	lower left X	LLY	lower left Y
FP5301	Graphtec FP5301	PM8151	Philips PM8151
HP7470A	HP 7470A	HP7550A	HP 7550A
HPQJ	HP QuietJet	HPTJ	HP ThinkJet
HPLJ	HP LaserJet	EPSON	Epson FX80
N L	Normal Low	NS	Non-standard

COMMAND SYNTAX

HardCopy_SetUp DEV,<device>, PORT,<port>
,SPEED,<plot_speed>,
 DENS,<print_density>, PENS,<plot_pens>,
 PFEED,<page_feed>, PSIZE,<paper_size>,
 GRID,<grid_square>, LLX,<lower_left_X>,
 LLY,<lower_left_Y>

Note: Parameters are grouped in pairs. The first one names the variable to be modified and the second one gives the new value to be assigned. Pairs may be given in any order and may be restricted to those variables to be changed.

<device> := {FP5301, PM8151, HP7470A, HP7550A, HPQJ, HPTJ, HPLJ, EPSON}

<port> := {GPIB, RS}

<plot_speed> := {N, L}

for plotters only

<density> := {SINGLE, DOUBLE, QUADRUPLE, HIGH_SPEED, HIGH_RESOLUTION, ONE_TO_ONE, TWO_TO_ONE,CRT}

for printers only

<plot_pens> := 1 to 8

<page_feed> := {ON, OFF}

<paper_size> := {A5, A4, A3, NS}

<grid_square> := 0.0 to 99.9 MM ` paper size only <lower left Y>:= -999 to 999 MM/

Note: For these three parameter values the suffix is optional. The suffix M is assumed.

QUERY SYNTAX

HardCopy_SetUp?

Response format

HardCopy_SetUp DEV, <device >, PORT, <port >, SPEED, <plot_speed>,DENS, <print_density>,PENS, <plot_pens>, PFEED,<page_feed>,PSIZE,<paper_size>,GRID,<grid_square>, LLX,<lower_left_X>,LLY,<lower_left_Y>

EXAMPLE (GPIB)

This example selects a HP 7550A plotter to be driven by the GPIB

port.

CMD\$="HCSU PORT,GPIB,DEV,HP7550A"

CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

HARDCOPY TRANSMIT, SCREEN DUMP

HARD COPY

HARDCOPY_TRANSMIT, HCTR

Command

DESCRIPTION

The HARDCOPY_TRANSMIT command sends a string of ASCII characters without modification to the hard-copy unit. This allows the user to control the hard-copy unit by sending device specific control character sequences. It also allows the user to place additional text on a screen dump for documentation purposes. This command accepts the escape sequence "\ddd" like those described under the command COMM RS232 (see page 56). Before sending the string to the hard-copy unit the escape sequence is converted to the ASCII character code.

COMMAND SYNTAX

HardCopy_TRansmit '<string>'

<string> := Any sequence of ASCII or escaped characters.

EXAMPLE (GPIB)

The following code sends documentation data to a printer.

CMD\$="HCTR 'Data from Oct.15\r\n'"

CALL IBWRT(SCOPE%,CMD\$)

The following code sends the same documentation data to an HP7470A plotter using pen 1. The text will be printed at the lower left corner of the paper.

CMD\$=

"HCTR 'IN;SP1;PA0,0;PD;LBData from Oct.15 \03IN;SP0;PA0,0'"

CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

HARDCOPY_SETUP, SCREEN_DUMP

HOR_MAGNIFY, HMAG

Command/Query

DESCRIPTION

The HOR MAGNIFY command horizontally expands the selected expansion trace by a specified factor. Magnification factors which are not within the range of permissible values will be rounded to the closest legal value.

If multiple zoom is enabled, the magnification factor for all expansion traces is set to the specified factor. If the specified factor is too large for any of the expanded traces (depending on their current source), it is reduced to an acceptable value and only then applied to the traces.

The VAB bit (bit 2) in the STB register (Table 8, page 121) is set if a factor outside the legal range is specified.

The HOR MAGNIFY query returns the current magnification factor for the specified expansion function.

COMMAND SYNTAX

<exp_trace>:Hor_MAGnify <factor>

 $\langle exp_trace \rangle := \{EA, EB, MC\ddagger, MD\ddagger\}$

<factor> := 1 to 1000

QUERY SYNTAX

<exp_source>:Hor_MAGnify?

Response Format

<exp source>:Hor MAGnify <factor>

EXAMPLE (GPIB)

The following example horizontally magnifies Expand B (EB) by a

factor of 5.

CMD\$="EB:HMAG 5": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

DUAL ZOOM, ZOOM

HOR_POSITION, HPOS

Command/Query

DESCRIPTION

The HOR_POSITION command horizontally positions the geometric center of the intensified zone on the source trace. Allowed positions range from division 0 through 10. If the source trace was acquired in sequence mode, horizontal shifting will only apply to a single segment at a time.

If the multiple zoom is enabled, the difference between the specified and the current horizontal position of the specified trace is applied to all expanded traces. If this would cause the horizontal position of any expanded trace to go outside the left or right screen boundaries, the difference of positions is adapted and then applied to the traces.

If the sources of expanded traces are sequence waveforms, and the multiple zoom is enabled, the difference between the specified and the current segment of the specified trace is applied to all expanded traces. If this would cause the segment of any expanded trace to go outside of the range of the number of segments of sources, the difference is adapted and then applied to the traces.

The VAB bit (bit 2) in the STB register (Table 8, page 121) is set if a value outside the legal range is specified.

The HOR_POSITION query returns the position of the geometric center of the intensified zone on the source trace.

COMMAND SYNTAX

<exp_trace>:Hor_POSition <hor position>,<segment>

 $\langle exp_trace \rangle := \{EA, EB, MC\ddagger, MD\ddagger\}$

<hor position> := 0 to 10 DIV

 $\langle segment \rangle := 1 to 200$

Note 1: The suffix DIV is optional.

Note 2: The segment number is only relevant for waveforms acquired in sequence mode. The segment number is ignored in single waveform acquisitions.

QUERY SYNTAX <exp_trace>:Hor_POSition?

Response Format <exp_trace>:Hor_POSition <hor_position>,[<segment>]

Note: The segment number is only given for sequence waveforms.

EXAMPLE (GPIB) The following example positions the center of the intensified zone

on the trace currently viewed by Expand A (EA) at division 3.

CMD\$="EA:HPOS 3": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS DUAL_ZOOM, ZOOM

MISCELLANEOUS

*IDN?

Query

DESCRIPTION

The *IDN? query is used for identification purposes. The response consists of four different fields providing information on the manufacturer, the scope model, the serial number and the firmware revision level.

QUERY SYNTAX

*IDN?

Response format

*IDN LECROY,<model>,<serial_number>,<firmware_level>

<model>

:= 5-character model identifier

<serial number> := an 8-digit decimal code (94xxxxxx)

<firmware_level> := 2 digits giving the release level followed by a

period and a 1-digit update level (xx.y)

EXAMPLE (GPIB)

This example issues an identification request to the scope.

CMD\$="*IDN?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message

*IDN LECROY,9450_,94501153,02.2

STATUS

INE

Command/Query

DESCRIPTION

The INE command sets the Internal state change Enable register (INE). This command allows one or more events in the INR register to be reflected in the INB summary message bit (bit 0) of the STB register. For an overview of the INR defined events refer to Table 7, page 95.

The INE? query reads the contents of the INE register.

Note: This command can be executed in both local and remote

modes.

COMMAND SYNTAX

INE <value>

<value> := 0 to 65 535

QUERY SYNTAX

INE?

Response format

INE <value>

EXAMPLE (GPIB)

The following command allows the INB bit to be set whenever a screen dump has finished (bit 1, i.e. decimal 2) and/or a waveform has been acquired (bit 0, i.e. decimal 1). Summing these two values

ues yields the INE mask 2+1=3.

CMD\$="INE 3": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

INR?

STATUS

INR?

Query

DESCRIPTION

The INR? query reads and clears the contents of the INternal state change Register (INR). The INR register (Table 7) keeps track of the completion of various internal operations and state transitions.

QUERY SYNTAX

INR?

Response format

INR <state>

<state> := 0 to 65535

EXAMPLE (GPIB)

The following instruction reads the contents of the INR register.

CMD\$="INR?": CALL IBWRT(SCOPE%,CMD\$)

Response message: INR 1026

i.e. waveform processing in Function E and a screen dump have

both terminated.

RELATED COMMANDS

ALL_STATUS?, *CLS, INE

Bit	Bit Value	Description	
1512		0 Reserved for future use	
11	2048	1 waveform processing has terminated in Function F	
10	1024	1 waveform processing has terminated in Function E	
9	512	1 waveform processing has terminated in Memory D‡	
8	256	1 waveform processing has terminated in Memory C‡	
74		0 Reserved for future use	
3	8	1 a time-out has occurred in a data block transfer	
2	4	1 a return to the local state is detected	
1	2	1 a screen dump has terminated	
0	1	1 a new signal has been acquired	

Internal State Register Structure (INR) Table 7

^{‡ 9424} only, reserved in 9420/50

WAVEFORM TRANSFER

INSPECT?, INSP?

Query

DESCRIPTION

The INSPECT? query allows the user to read parts of an acquired waveform in intelligible form. The command is based on the explanation of the format of a waveform given by the template (use the query TEMPLATE? to obtain an up-to-date copy). Each logical block of a waveform may be inspected by giving its name (e.g. TRIGTIME as mentioned in the template) enclosed in quotes as the first (string) parameter.

The special logical block named WAVEDESC may also be inspected in more detail. By giving the name of a variable in the block WAVEDESC enclosed in quotes as the first (string) parameter, it is possible to inspect only the actual value of that variable.

Notation

BYTE: raw data as integers (truncated to 8 m.s.b.*)

WORD: raw data as integers (truncated to 16 m.s.b.*)

FLOAT: normalized data (gain, offset applied) as floating

point numbers (gives measured values in volts or appropriate units)

* most significant bits

QUERY SYNTAX

<trace>:INSPect? '<string>'[,<data_type>]

<trace> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}

<data type> := {BYTE, WORD, FLOAT}

Note: The optional parameter <data_type> applies only for inspecting the data arrays. It selects the representation of the data. The default <data type> is FLOAT.

Response format

<trace>:INSPect "<string>"

‡ 9424 only

EXAMPLES (GPIB)

1) The following command reads the value of the time base at which the last waveform in Channel 1 was acquired.

CMD\$:="C1:INSP? 'TIMEBASE'" CALL IBWRT(SCOPE%,CMD\$) CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message C1:INSP "TIMEBASE: 500 US/DIV"

2) The following command reads the entire contents of the waveform descriptor block.

CMD\$ = "C1:INSP? 'WAVEDESC'"

RELATED COMMANDS

TEMPLATE, WAVEFORM_SETUP

INTENSITY, INTS

Command/Query

DESCRIPTION

The INTENSITY command sets the intensity level of the grid or the trace/text provided the local control of the intensity has been turned off. Note that normally the screen intensity is still under manual control when the oscilloscope operates remotely. The local intensity control has to be turned off (using the command INTS LOCAL,OFF) before the intensity levels can be modified remotely.

The intensity level is expressed as a percentage (PCT). A level of 100 PCT corresponds to the maximum intensity while a level of 0 PCT sets the intensity to its minimum value.

The response to the INTENSITY? query indicates the grid and trace intensity levels and their control mode.

COMMAND SYNTAX

INTenSity LOCAL, < mode > , GRID, < value > , TRACE, < value >

<mode> := {ON, OFF} <value> := 0 to 100 PCT

Note 1: Parameters are grouped in pairs. The first one names the variable to be modified and the second one gives the new value to be assigned. Pairs may be given in any order and may be restricted to those variables to be changed.

Note 2: The suffix PCT is optional.

QUERY SYNTAX

INTenSity?

Response Format

INTenSity LOCAL, < mode>, TRACE, < value>, GRID, < value>

EXAMPLE (GPIB)

The following instruction enables remote control of the intensity and changes the grid intensity level to 75%.

CMD\$="INTS LOCAL,OFF,GRID,75" CALL IBWRT(SCOPE%,CMD\$)

The following instruction re-enables local control of the intensity.

CMD\$=INTS LOCAL,ON"
CALL IBWRT(SCOPE%,CMD\$)

ACQUISITION

INTERLEAVED, ILVD

Command/Query

DESCRIPTION

The INTERLEAVED command enables or disables random interleaved sampling (RIS). RIS is available at time-base settings faster than or equal to 5 µsec/div (9450) or 20 µsec/div (9420/24). An environment error (Table 6, page 82) will be generated if the user attempts to turn off RIS at time-base settings faster than or equal to 5 nsec/div (9450) or 20 nsec/div (9420/24), or to turn RIS on at time-base settings slower than 5 µsec/div (9450) or 20 µsec/div (9420/24).

RIS is not available for sequence mode acquisitions and therefore an attempt to turn it on in that mode will also result in an environment error.

The response to the INTERLEAVED? query indicates whether the oscilloscope is in the RIS mode.

COMMAND SYNTAX

InterLeaVeD < mode>

 $< mode > := \{ON, OFF\}$

QUERY SYNTAX

InterLeaVeD?

Response Format

InterLeaVeD <mode>

EXAMPLE

The following command sets the oscilloscope into RIS mode.

CMD\$ = "ILVD ON": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TIME_DIV, TRIG_MODE

STATUS

*IST?

Query

DESCRIPTION

The *IST? (Individual STatus) query reads the current state of the IEEE 488.1 defined "ist" local message. The "ist" individual status message is the status bit sent during a parallel poll operation.

QUERY SYNTAX

*IST?

Response format

*IST <value>

<value> := 0 or 1

EXAMPLE (GPIB)

The following command reads the contents of the IST bit:

CMD\$ = "*IST?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%, RSP\$): PRINT RSP\$

Response message

*IST 0

RELATED COMMANDS

*PRE

KEY

Command

DESCRIPTION


The KEY command is used to display a string in the menu field next to one of the 9 menu buttons. The string may consist of up to 12 characters and may be positioned at 4 different locations: above (L1), opposite (LC), or below (L2) the menu buttons; or (LB) between pairs of buttons, ([1,2], [3,4], [5,6] or [7,8]). See Figure 1.

Note: The button names shown in Figure 1 are not the same as those indicated in the front-panel figure at the beginning of the Operator's Manual.

Texts assigned to the menu buttons will disappear on the next transition to local but reappear when the instrument is switched back into the remote state. The texts are cleared at power up, when the rear-panel RESET button (64) is pressed or if an empty string is assigned to a location (e.g. KEY " ",L1).

Pressing any one of the menu buttons while in remote mode causes the User Request status Register (URR) and the URQ bit of the Event Status Register to be set. This can generate an SRQ provided that the service request mechanism has been enabled.

Note: This command can be executed in both local and remote modes.



COMMAND SYNTAX

KEY <button>,'<string>',<position>

<button> := 1 to 9

<string> := a 12 character string (any ASCII code)

 $\langle position \rangle := \{L1, LC, L2, LB\}$

Note: If the position is omitted, LC will be assumed.

EXAMPLE (GPIB)

This example will display the message "Continue" on the upper

line in the menu field of button 1.

CMD\$="KEY 1,'CONTINUE',L1" CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

URR?

DISPLAY

MESSAGE, MSG

Command/Query

DESCRIPTION

The MESSAGE command displays a string of characters in the Message Field above the grid. The string may be up to 45 characters in length. The string is displayed as long as the instrument is in remote mode and no internal status message is generated. Turning the oscilloscope back to local mode deletes the message. After the next transition from local to remote the message will be redisplayed. The message is cleared at power up, when the RESET button ((64) in the 9420/50, (71) in the 9424) is pressed or if an empty string is sent (MSG "").

The MESSAGE? query allows the user to read the last message which was sent.

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

MeSsaGe '<string>'

<string> := a string of max. 45 characters

QUERY SYNTAX

MeSsaGe?

Response Format

MeSsaGe "<string>"

EXAMPLE (GPIB)

The following code causes the message "*Connect Probe 1*" to appear in the message field.

CMD\$="MSG '*Connect Probe 1*'"
CALL IBWRT(SCOPE%,CMD\$)

DISPLAY

MULTI ZOOM, MZOM

Command/Query

DESCRIPTION By setting MULTI_ZOOM ON, the horizontal magnification and

positioning controls apply to all expanded traces simultaneously. This command is useful if the contents of all expanded traces are

to be examined at the same time.

The MULTI_ZOOM? query indicates whether multiple zoom is

enabled or not.

Note: This command has the same effect as DUAL_ZOOM.

Multi ZOoM <mode> **COMMAND SYNTAX**

 $< mode > := \{ON, OFF\}$

QUERY SYNTAX Multi_ZOoM?

Response format Multi_ZOoM <mode>

EXAMPLE (GPIB) The following example turns the multiple zoom on.

CMD\$="MZOM ON": CALL IBWRT(SCOPE%,CMD\$)

HOR_MAGNIFY, HOR_POSITION, DUAL_ZOOM, ZOOM RELATED COMMANDS

OFFSET, OFST

Command/Query

DESCRIPTION

The OFFSET command allows the vertical offset of the specified input channel to be adjusted.

The maximum ranges depend on the fixed sensitivity setting as follows:

Fixed Sensitivity	Offset Range	Voltage
1 V	土 10 times	± 10V
0.5 V to 20 mV	土 12 times	± 6 V to ± 240 mV
10 mV	\pm 24 times	± 240 mV
5 mV	± 48 times	± 240 mV

If an out-of-range value is entered, the oscilloscope is set to the closest possible value and the VAB bit (bit 2) in the STB register is

Note: The probe attenuation factor is not taken into account for adjusting the offset.

The OFFSET? query returns the DC offset value of the specified channel.

COMMAND SYNTAX

<channel>:OFfSeT <offset>

<channel $> := \{C1, C2, C3‡, C4‡\}$

<offset> := -10V to 10V (maximum range)

Note: The suffix V is optional.

QUERY SYNTAX

<channel>:OFfSeT?

Response format

<channel>:OFfSeT <offset>

EXAMPLE (GPIB)

The following command sets the offset of Channel 2 to -3 V.

CMD\$="C2:OFST -3V": CALL IBWRT(SCOPE%,CMD\$)

‡ 9424 only

STATUS

*OPC

Command/Query

DESCRIPTION

The *OPC (OPeration Complete) command sets the OPC bit (bit 0) in the standard Event Status Register (ESR) to true. This command has no other effect on the operation of the oscilloscope as the instrument starts parsing a command or query only after it has completely processed the previous command or query.

The *OPC? query always responds with the ASCII character "1" as the oscilloscope responds to the query only once the previous command has been entirely executed.

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

*OPC

QUERY SYNTAX

*OPC?

Response format

*OPC 1

RELATED COMMANDS

*WAI

MISCELLANEOUS

*OPT?

Query

DESCRIPTION

The *OPT? query identifies oscilloscope options, i.e. additional firmware or hardware options. The response consists of a series of response fields listing all the installed options.

QUERY SYNTAX

*OPT?

Response format

*OPT <option_1>,<option_2>,..,<option_N>

<option_i> := character data

Note: If no option is present, the character 0 will be returned.

EXAMPLE (GPIB)

This example queries the installed options.

CMD\$="*OPT?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%,RSP\$): PRINT RSP\$

Response message

*OPT 0

If the waveform processing options WP01 and WP02 are installed,

the response message is

*OPT WP01, WP02

SAVE/RECALL SETUP

PANEL_SETUP, PNSU

Command/Query

DESCRIPTION

The PANEL_SETUP command complements the *SAV/*RST commands. The PANEL_SETUP command allows panel setups to be archived in encoded form on external storage media.

Only setup data read by the PNSU? query may be recalled into the oscilloscope. A panel setup error (see Table 6, page 82) will be generated if the setup data block contains invalid data.

Note: The communication parameters (those modified by commands CFMT, CHDR, CHLP, CORD and WFSU) and the enable registers associated with the status reporting system (SRE, PRE, ESE, INE) are not saved by this command.

COMMAND SYNTAX

PaNel SetUp <setup>

<setup> := A setup block previously read by PNSU?

QUERY SYNTAX

PaNel_SetUp?

Response syntax

PaNel SetUp <setup>

EXAMPLE (GPIB)

1. The following instruction saves the instrument's current panel setup in the file PANEL.SET.

FILE\$ = "PANEL.SET": CMD\$ = "PNSU?"

CALL IBWRT(SCOPE%,CMD\$)
CALL IBRDF(SCOPE%,FILE\$)

2. The following command recalls the front-panel setup stored previously in the file PANEL.SET into the oscilloscope.

CALL IBWRTF(SCOPE%,FILE\$)

RELATED COMMANDS

*RCL, *SAV

CURSOR

PARAMETER_VALUE?, PAVA?

Query

DESCRIPTION

The PARAMETER_VALUE? query returns the current value(s) of the pulse waveform parameter(s) for the specified trace. Traces do not need to be displayed or selected to obtain the values measured by the pulse parameters.

Pulse parameters cannot be evaluated on waveforms composed of segments acquired in sequence mode. However pulse parameters may be applied to individual segments if they are singled out using the expansion function.

Parameter Names

FRST	first point	LAST	last point
PNTS	points	MIN	minimum
MAX	maximum	MEAN	mean
SDEV	std deviation	RMS	root mean sq
DLY	delay	PER	period
WID	width	RISE	risetime
FALL	falltime	ALL	all parameters

Parameter Computation States

OK	deemed to be determined without problem		
ΑV	averaged over several (up to 100) periods		
PT	window has been period truncated		
IV	invalid value (insufficient data provided)		
NP	no pulse waveform		
LT	less than given value		
OF	signal partially in overflow		
UF	signal partially in underflow		
OU	signal partially in overflow and underflow		
Saa tha anarator's manual Figura 10			

See the operator's manual Figure 19.

QUERY SYNTAX

<trace>:PArameter_VAlue? [<parameter>, ... <parameter>] <trace> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡} <parameter> := {FRST, LAST, PNTS, MIN, MAX, MEAN, SDEV, RMS, DLY, PER, WID, RISE, FALL, ALL}

Response Format

<trace>:PArameter_VAlue <parameter>,<value>,<state>[,... ,<parameter>,<value>,<state>]

‡ 9424 only

<value> := decimal numeric value

<state> := {OK, AV, PT, IV, NP, LT, OF, UF, OU}

parameters followed by their values and states are returned.

EXAMPLE (GPIB)

The following query reads the risetime of Expand B (EB).

CMD\$="EB:PAVA? RISE": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD (SCOPE%,RD\$): PRINT RD\$

Response message

"EB:PAVA RISE,3.6E-9S,OK"

RELATED COMMANDS

CURSOR_SET

STATUS

*PRE

Command/Query

DESCRIPTION

The *PRE command sets the PaRallel poll Enable register (PRE). The lowest 8 bits of the Parallel Poll Register (PPR) are composed of the STB bits. The *PRE command allows the user to specify which bit(s) of the parallel poll register will affect the 'ist' individual status bit.

The *PRE? query reads the contents of the PRE register. The response is a decimal number which corresponds to the binary sum of the register bits.

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

PRE <value>

<value> := 0 to 65 535

QUERY SYNTAX

*PRE?

Response format

*PRE <value>

EXAMPLE (GPIB)

The following command will cause the 'ist' status bit to become 1 as soon as the MAV bit (bit 4 of STB, i.e. decimal 16) is set. This

yields the PRE value 16.

CMD\$="*PRE 16": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

*IST?

SAVE/RECALL SETUP

*RCL

Command

DESCRIPTION

The *RCL command sets the state of the instrument using one of the eight non-volatile panel setups by recalling the complete front-panel setup of the instrument. Panel setup 0 corresponds to the default panel setup.

The *RCL command produces the opposite effect of the *SAV command.

If the desired panel setup is not acceptable, the Execution error status Register (EXR) is set and the EXE bit of the standard Event

Status Register (ESR) is set.

COMMAND SYNTAX

*RCL <panel_setup>

<panel_setup> := 0 to 7

EXAMPLE (GPIB)

The following code recalls the instrument setup previously stored

in panel setup 5

CMD\$="*RCL 5": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

PANEL_SETUP, *SAV, EXR?

SAVE/RECALL SETUP

*RST

command

DESCRIPTION

The *RST command initiates a device reset. The *RST sets all 8 traces to the GND line, recalls the default setup and causes a cali-

bration to be performed.

COMMAND SYNTAX

*RST

EXAMPLE (GPIB)

This example resets the oscilloscope

CMD\$="*RST": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

*CAL?, *RCL

SAMPLE_CLOCK, SCLK

Command/Query

DESCRIPTION

The SAMPLE_CLOCK command allows the user to control the use of an external time base. The user sets the number of data points that will be acquired when the oscilloscope is using the external clock.

COMMAND SYNTAX

Sample_CLocK <state>[,<recordlength>]

Note: If <recordlength> is not specified the previous value will not be modified. (The parameter <recordlength> is initially set to 50000).

QUERY SYNTAX

Sample_CLocK?

Response Format

Sample_CLocK <state>,<recordlength>

EXAMPLE

The following command sets the oscilloscope to use the external

clock with 1000 data point records.

CMD\$ = "SCLK EXT,1000": CALL IBWRT(SCOPE%,CMD\$)

SAVE/RECALL SETUP

*SAV

Command

DESCRIPTION

The *SAV command stores the current state of the instrument in non-volatile internal memory. The *SAV command stores the complete front-panel setup of the instrument at the time the command is issued.

Note: The communication parameters (those modified by commands CFMT, CHDR, CHLP, CORD and WFSU) and the enable registers associated with the status reporting system (SRE, PRE, ESE, INE) are not saved by this command.

COMMAND SYNTAX

*SAV <panel_setup>

<panel setup> := 1 to 7

EXAMPLE (GPIB)

The following code saves the current instrument setup in panel

setup 5.

CMD\$="*SAV 5": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

PANEL_SETUP, *RCL

HARD COPY

SCREEN_DUMP, SCDP

Command/Query

DESCRIPTION

The SCREEN_DUMP causes the oscilloscope to dump the screen contents onto the hard copy device. For plotting, this command will not halt oscilloscope activities since plotting is performed in parallel with other tasks, unless it is done over the same port as the remote control. Printing, however, cannot be done in parallel with other oscilloscope operations.

Screen dumps may be aborted by adding [A] to the screen dump command, as shown in the command syntax below.

The time/date stamp which appears on the plot corresponds to the time at which the command was executed.

The SCREEN_DUMP? query indicates whether a screen dump is currently in progress (ON) or has finished (OFF).

COMMAND SYNTAX

SCreen_DumP [A]

Note: The optional parameter "A" may be used to abort a screen dump.

QUERY SYNTAX

SCreen DumP?

Response format

SCreen_DumP <status>
<status> := {ON, OFF}

EXAMPLE (GPIB)

The following code initiates a screen dump.

CMD\$="SCDP"; CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

INR?, HARDCOPY_SETUP, HARDCOPY_TRANSMIT

SEGMENTS, SEGS

Command/Query

DESCRIPTION

The SEGMENTS command sets the number of segments for se-

quence mode acquisition.

The response to the SEGMENTS? query indicates the number of

segments which is set in the oscilloscope.

COMMAND SYNTAX

SEGmentS <segments>

 $\langle segments \rangle := \{2, 5, 10, 20, 50, 100, 200\}$

QUERY SYNTAX

SEGmentS?

Response Format

SEGmentS <segments>

EXAMPLE

The following command sets the segment count to 100.

CMD\$ = "SEGS 100": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TRIG_MODE

DISPLAY

SELECT, SEL

Command/Query

DESCRIPTION

The SELECT command selects the specified trace for manual display control. An environment error (Table 6, page 82) is

generated if the specified trace is not displayed.

The SELECT? query returns the selection status of the specified

trace.

COMMAND SYNTAX

<trace>:SELect

<trace> := {EA, EB, MC, MD, FE, FF}

QUERY SYNTAX

<trace>:SELect?

Response format

<trace>:SELect <mode>

 $< mode > := {ON, OFF}$

EXAMPLE (GPIB)

The following command selects Expand B (EB).

CMD\$="EB:SEL": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TRACE

STATUS

*SRE

Command/Query

DESCRIPTION

The *SRE command sets the Service Request Enable register (SRE). This command allows the user to specify which summary message bit(s) in the STB register will generate a service request. Refer to Table 8, page 121 for an overview of the available summary messages.

A summary message bit is enabled by writing a 1 into the corresponding bit location. Conversely, writing a 0 into a given bit location prevents the associated event from generating a service request (SRQ). Clearing the SRE register disables SRQ interrupts.

The *SRE? query returns a value which when converted to a binary number represents the bit settings of the SRE register. Note that bit 6 (MSS) cannot be set and its returned value is always zero.

Note: This command can be executed in both local and remote modes.

COMMAND SYNTAX

*SRE <value>

<value> := 0 to 255

QUERY SYNTAX

*SRE?

Response format

*SRE <value>

EXAMPLE (GPIB)

The following command allows an SRQ to be generated as soon as the MAV summary bit (bit 4, i.e. decimal 16) and/or the INB summary bit (bit 0, i.e. decimal 1) in the STB register are set. Summing these two values yields the SRE mask 16 + 1 = 17.

CMD\$="*SRE 17": CALL IBWRT(SCOPE%,CMD\$)

STATUS

*STB?

Query

DESCRIPTION

The *STB? query reads the contents of the 488.1 defined status register (STB), and the Master Summary Status (MSS). The response represents the values of bits 0 to 5 and 7 of the Status Byte register and the MSS summary message.

The response to a *STB? query is identical to the response of a serial poll except that the MSS summary message appears in bit 6 in place of the RQS message. Refer to Table 8, page 121 for further details on the status register structure.

QUERY SYNTAX

*STB?

Response format

*STB <value>

<value> := 0 to 255

EXAMPLE (GPIB)

The following instruction reads the status byte register.

CMD\$="*STB?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%,RSP\$): PRINT RSP\$

Response message

*STB 0

RELATED COMMANDS

ALL_STATUS?, *CLS, *PRE, *SRE

Bit	Value	Name	Description	Note
7	128	Di07	0 Reserved for future use	
6	64	MSS/RQS MSS =1 RQS =1	at least 1 bit in STB masked by SRE is 1 service is requested	(1) (2)
5	32	ESB	1 an ESR enabled event has occurred	(3)
4	16	MAV	1 Output queue is not empty	(4)
3	8	DIO3	0 Reserved	В
2	4	VAB	1 a command data value has been adapted	(5)
1	2	DIO1	0 Reserved	
0	1	INB	an enabled INternal state change has occurred.	(6)

Status Byte Register (STB)

Table 8

Notes:

(1) The Master Summary Status (MSS) indicates that the instrument requests service while the Service Request status – when set – specifies that the oscilloscope Issued a service request. Bit position 6 depends on the polling method:

Bit 6 = MSS if a *STB? query is received = RQS if serial polling is conducted

- (2) Example: If SRE = 10 and STB = 10 then MSS = 1. If SRE = 010 and STB = 100 then MSS=0.
- (3) The Event Status Bit (ESB) indicates whether or not one or more of the enabled IEEE 488.2 events have occurred since the last reading or clearing of the Standard Event Status Register (ESR). ESB is set if an enabled event becomes true (1).
- (4) The Message AVallable bit (MAV) indicates whether or not the Output queue is empty. The MAV summary bit is set true (1) whenever a data byte resides in the Output queue.
- (5) The Value Adapted Bit (VAB) Is set true (1) whenever a data value in a command has been adapted to the nearest legal value. For instance, the VAB bit would be set if the time base is redefined as 2.5 μsec/div since the adapted value is 2 μsec/div.
- (6) The INternal state Bit (INB) is set true (1) whenever certain enabled internal states are entered. For further information, refer to the INR? query.

STOP

Command

DESCRIPTION

The STOP command immediately stops the acquisition of a signal. It changes the acquisition state from "ready" to "triggered", and if the trigger mode is AUTO or NORM it will change to trigger mode

SINGLE to prevent further acquisition.

COMMAND SYNTAX

STOP

EXAMPLE

The following command stops the acquisition process.

CMD\$ = "STOP": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

ARM_ACQUISITION, TRIG_MODE, WAIT

WAVEFORM TRANSFER

STORE, STO

Command

DESCRIPTION

The STORE command stores the contents of the specified trace into one of the internal function memories, Memory C,

Memory D, Function E‡ or Function F‡.

COMMAND SYNTAX

<memory> STOre <trace>

<memory $> := \{MC, MD, FE‡, FF‡\}$

<trace> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}

EXAMPLE (GPIB)

The following command stores the contents of Expand B (EB) into

Memory D (MD).

CMD\$="MD:STO EB": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

FUNCTION_STATE‡

WAVEFORM TRANSFER

TEMPLATE?, TMPL?

Query

DESCRIPTION The TEMPLATE? query produces a copy of the template which

formally describes the various logical entities making up a complete waveform. In particular, the template describes in full detail the variables contained in the descriptor part of a waveform. Refer

to Section 6 for further information.

TeMPLate? **QUERY SYNTAX**

TeMPLate "<template>" Response format

<template> := A variable length string detailing the structure of

a waveform.

RELATED COMMANDS INSPECT?

TIME_DIV, TDIV

Command/Query

DESCRIPTION

The TIME_DIV command modifies the time-base setting. The new time-base setting may be specified with suffixes NS for nanoseconds, US for microseconds, MS for milliseconds, S for seconds or KS for kiloseconds. An out-of-range value causes the VAB bit (bit 2) in the STB register (Table 8, STB) to be set.

The oscilloscope will force random interleaved sampling (RIS) for time-base settings faster than or equal to 5 nsec/div (9450) or 20 nsec/div (9420/24) and single-shot sampling for time-base settings slower than or equal to 10 μ sec/div (9450) or 50 μ sec/div (9420/24). Within this range the INTERLEAVED command allows the user to choose the required sampling mode.

Sequence mode acquisitions also force single-shot sampling and are therefore restricted to time-base values slower than or equal to 10 nsec/div (9450) or 50 nsec/div (9420/24). In sequence mode an environment error (Table 6, page 82) will be generated if the user attempts to set the time base to a faster value.

The TIME_DIV? query returns the current time-base setting.

COMMAND SYNTAX

Time DIV <value>

 $\langle value \rangle := 1 NS to 5 KS$

Note: The suffix S (seconds) is optional.

QUERY SYNTAX

Time_DIV?

Response Format

Time_DIV <value>

EXAMPLE (GPIB)

The following command sets the time base to 500 µsec/div. CMD\$="TDIV 500US": CALL IBWRT(SCOPE%,CMD\$) The following command sets the time base to 2 msec/div. CMD\$="TDIV.002": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

INTERLEAVED, TRIG_DELAY, TRIG_MODE

DISPLAY

TRACE, TRA

Command/Query

DESCRIPTION

The TRACE command enables or disables the display of a trace. An environment error (Table 6, page 82) is set if an attempt is

made to display more than four waveforms.

The TRACE? query indicates whether the specified trace is dis-

played or not.

COMMAND SYNTAX

<trace>:TRAce <mode>

<trace> := {C1, C2, C3‡, C4‡, EA, EB, MC, MD, FE, FF}

<mode $> := {ON, OFF}$

QUERY SYNTAX

<trace>:TRAce?

Response format

<trace>:TRAce <mode>

EXAMPLE (GPIB)

The following command displays Function E (FE).

CMD\$="FE:TRA ON": CALL IBWRT(SCOPE%,CMD\$)

*TRG

Command

DESCRIPTION

The *TRG command executes an ARM command.

Note: The *TRG command is the equivalent of the 488.1 GET

(Group Execute Trigger) message.

COMMAND SYNTAX

*TRG

EXAMPLE (GPIB)

The following command enables signal acquisition.

CMD\$="*TRG": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

ARM_ACQUISITION, STOP, WAIT

TRIG_COUPLING, TRCP

Command/Query

DESCRIPTION

The TRIG_COUPLING command sets the coupling mode of the specified trigger source. The trigger slope is automatically changed to positive when the trigger coupling is set to HFDIV.

Note: HFDIV is indicated as HF on the front panel. See the Operator's Manual, Section 5 (9424) or Section 6 (9450/20). The TRIG_COUPLING? query returns the trigger coupling of the

selected source.

COMMAND SYNTAX

<trig_source>:TRig_CouPling <trig_coupling>

<trig_source> := {C1, C2, EX†&, EX10†, C4‡}

<trig_coupling> := {AC, DC, HFREJ, LFREJ, HFDIV}

QUERY SYNTAX

<trig_source>:TRig_CouPling?

Response format

<trig_source>:TRig_CouPling <trig_coupling>

EXAMPLE (GPIB)

The following command sets the coupling mode of the trigger

source Channel 2 to high frequency reject.

CMD\$="C2:TRCP HFREJ": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TRIG_SELECT

TRIG DELAY, TRDL

Command/Query

DESCRIPTION

The TRIG DELAY command sets the time at which the trigger is to occur with respect to the first acquired data point (displayed at the left hand edge of the screen).

The command expects positive trigger delays to be expressed as a percentage of the full horizontal screen (this mode is called pretrigger acquisition as data are acquired before the trigger occurs). Negative trigger delays must be given in seconds (this mode is called post-trigger acquisition as the data are acquired after the trigger has occurred).

If a value outside the range $-10\ 000\ div \times time/div$ and 100% is specified, the trigger time will be set to the nearest limit and the VAB bit (bit 2) will be set in the STB register.

The response to the TRIG_DELAY? query indicates the trigger time with respect to the first acquired data point. Positive times are expressed as a percentage of the full horizontal screen and negative times in seconds.

COMMAND SYNTAX

TRig_DeLay <value>

<value> := 0.00 PCT to 100.00 PCT (pretrigger) -20 PS to -50 MAS (post-trigger)

Note: The suffix is optional. For positive numbers the suffix PCT is assumed. For negative numbers the suffix S is assumed. MAS is the suffix for Msec (megaseconds), useful only for extremely large delays at very slow time bases.

QUERY SYNTAX

TRig DeLay?

Response format

TRig DeLay <value>

EXAMPLE (GPIB)

The following command sets the trigger delay to - 20 sec (posttrigger)

CMD\$="TRDL -20S": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TIME DIV

TRIG_LEVEL, TRLV

Command/Query

DESCRIPTION

The TRIG_LEVEL command adjusts the trigger level of the specified trigger source. An out-of-range value will be adjusted to the closest legal value and will cause the VAB bit (bit 2) in the STB register (Table 8, page 121) to be set.

The range of values is as follows:

 \pm 5 times the total V/div setting – with CHAN 1 or CHAN 2 as the trigger source

 \pm 2 V with EXT as trigger source for 9420 and 9450 \pm 0.8 V with EXT as trigger source for 9424 with ext. trigger option

 \pm 20 V with EXT/10 as trigger source

The TRIG_LEVEL? query returns the current trigger level.

COMMAND SYNTAX

<trig source>:TRig LeVel <trig level>

<trig_source> := {C1, C2, EX†&, EX10†, C4‡} $\langle \text{trig level} \rangle := -20 \text{V to } 20 \text{V (maximum range)}$

Note: The suffix V is optional.

QUERY SYNTAX

<trig source>:TRig_LeVel?

Response format

<trig source>:TRig LeVel <trig level>

EXAMPLE (GPIB)

The following command adjusts the trigger level of Channel 2 to

-3.4 V.

CMD\$="C2:TRLV -3.4V": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TRIG_SELECT

[‡] standard 9424 only, † 9420/50 only, & 9424 with ext. trigger option

TRIG_MODE, TRMD

Command/Query

DESCRIPTION

The TRIG_MODE command specifies the trigger mode. An environment error (Table 6, page 82) will be generated when TRMD SEQNCE is received while the instrument is in the interleaved sampling (RIS) acquisition mode. With the mode SINGLE, this command will not arm the trigger. Use the command ARM_AC-

QUISITION to actually start a single acquisition.

The TRIG_MODE? query returns the current trigger mode.

COMMAND SYNTAX

TRig_MoDe <mode>

<mode> := {AUTO, NORM, SEQNCE, SINGLE, WRAP}

QUERY SYNTAX

TRig_MoDe?

Response format

TRig_MoDe <mode>

EXAMPLE (GPIB)

The following command selects the sequence mode.

CMD\$="TRMD SEQNCE": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

ARM_ACQUISITION, STOP, TRIG_SELECT

TRIG_PATTERN, TRPA (9420/50 and 9424 with ext. trigger option)

7424 With ext. trigger option)

Command/Query

DESCRIPTION

The TRIG_PATTERN command defines a trigger pattern. The command specifies the logic composition of the pattern sources (Channel 1, Channel 2, External) and the conditions under which a trigger can occur. Note that this command can be used even if the complex trigger mode has not been activated.

Notation

L Low

H High

X Don't Care

PR pattern present

AB pattern absent

EN pattern entered

EX pattern exited

The TRIG_PATTERN? query returns the current trigger pattern.

COMMAND SYNTAX

TRig_PAttern <C1_state>,<C2_state>,<EX_state>,<trig_conditions

tion>

 $\langle C1_state \rangle := \{L,H,X\}$

 $\langle C2_state \rangle := \{L,H,X\}$

 $\langle EX_state \rangle := \{L,H,X\}$

<trig_condition> := {PR, AB, EN, EX}

QUERY SYNTAX

TRig PAttern?

Response format

TRig_PAttern <C1_state>,<C2_state>,<EX_state>,<trig_condi-

tion>

EXAMPLE (GPIB)

The following command configures the logic state of the pattern as HLX (CH1 = H, CH2 = L, EX = X) and defines the trigger con-

dition as pattern absent (AB).

CMD\$="TRPA H,L,X,AB": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TRIG_SELECT

TRIG_PATTERN, TRPA (9424)

Command/Query

DESCRIPTION

The TRIG PATTERN command defines a trigger pattern. The command specifies the logic composition of the pattern sources (Channel 1, Channel 2, and Channel 4) and the conditions under which a trigger can occur. Note that this command can be used even if the complex trigger mode has not been activated.

Notation

Low

Н High

Χ Don't Care

PR pattern present AB pattern absent

EN pattern entered

EX pattern exited

The TRIG PATTERN? query returns the current trigger pattern.

COMMAND SYNTAX

TRig_PAttern <C1_state>,<C2_state>,<C4_state>,<trig_condi-

tion>

 $\langle C1 \text{ state} \rangle := \{L,H,X\}$

 $\langle C2_state \rangle := \{L,H,X\}$

 $\langle C4 \text{ state} \rangle := \{L,H,X\}$

<trig condition> := {PR, AB, EN, EX}

OUERY SYNTAX

TRig PAttern?

Response format

TRig_PAttern <C1_state>,<C2_state>,<C4_state>,<trig_condi-

tion>

EXAMPLE (GPIB)

The following command configures the logic state of the pattern as

HLX (CH1 = H, CH2 = L, CH4 = X) and defines the trigger con-

dition as pattern absent (AB).

CMD\$="TRPA H,L,X,AB": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TRIG_SELECT

TRIG_SELECT, TRSE (9420/50)

Command/Query

DESCRIPTION

The TRIG_SELECT command selects the condition that will trigger the acquisition of waveforms. Depending on the trigger type, additional parameters have to be specified.

The additional parameters are grouped in pairs. The first one names the variable to be modified and the second one gives the new value to be assigned. Pairs may be given in any order and may be restricted to those variables to be changed.

Note: The state-qualified, time/event qualified and pattern trigger types use the trigger pattern defined by the command TRIG-GER_PATTERN.

The TRIG_SELECT? query returns the current trigger condition.

Trigger Notation

STD	Standard	SNG	Single source
PA	Pattern	SQ	State qualified
TEQ	Time event qualified	TI	Time
PL	Pulse larger	IL.	Interval larger
EV	Event	PS	Pulse smaller
IS	Interval smaller	SR	Source
HT	Hold type	HV	Hold value

TV Trigger Notation

FLD	Field	FLDC	Field Count
LINE	Line	CHAR	Characteristics
LPIC	Lines per picture	ILAC	Interlace

SR does not apply to the Pattern trigger. HT and HV do not apply to the standard trigger.

COMMAND SYNTAX

<trig_type> := {STD, SNG, SQ, TEQ, PA} <source> := {C1, C2, LINE, EX, EX10} <hold_type> := {TI, EV, PS, PL, IS, IL} <hold_value> := 25NS to 20S for TI 1 to 109 for EV

2.5NS to 20S for PS and PL* 10NS to 20S for IS* 25NS to 20S for IL*

Note: The suffix S (seconds) is optional.

COMMAND SYNTAX

TV TRIGGER

TRig_SElect TV,SR,EX,FLDC,<field_count>,FLD,<field>, CHAR, <characteristics>, LPIC@, <lpic>, ILAC@, <ilace>, LINE, <line> LINE, <line>

<field_count> := {1, 2, 4, 8} <field> := 1 to field_count

<characteristics> := { NTSC,PALSEC,CUST50&,CUST60&}

<|pic> := 1 to 1500 $\langle ilace \rangle := \{1, 2, 4, 8\}$ < line> := 1 to 1500

Note: The FLD value is interpreted with the current FLDC value. The LINE value is interpreted with the current FLD and CHAR values.

QUERY SYNTAX

TRig_SElect?

Response format

TRig SElect <trig type>,SR,<source>,HT,<hold type>,

HV,<hold value>

TRig SElect TV, SR, EX, FLDC, < field count>, FLD, < field>,

CHAR, < characteristic > , LINE, < line >

EXAMPLE (GPIB)

The following command selects the single-source trigger with Channel 1 as trigger source. Hold type and hold value are chosen

as "Pulse smaller" than 20 µsec

CMD\$="TRSE SNG,SR,C1,HT,PS,HV,20 US"

CALL IBWRT(SCOPE%,CMD\$)

EXAMPLE: TV

CMD\$ = "TRSE TV,SR,EX,FLDC,8,FLD,3,CHAR,

PALSEC, LINE, 17"

RELATED COMMANDS

TRIG COUPLING, TRIG LEVEL, TRIG MODE, TRIG PAT-

TERN, TRIG_SLOPE

^{*} these values are only valid for single-source and pattern triggers.

[@] for CUST50 and CUST60 only, & for oscilloscopes with HDTV hardware option only

TRIG_SELECT, TRSE (9424)

Command/Query

DESCRIPTION

The TRIG_SELECT command selects the condition that will trigger the acquisition of waveforms. Depending on the trigger type, additional parameters have to be specified.

The additional parameters are grouped in pairs. The first one names the variable to be modified and the second one gives the new value to be assigned. Pairs may be given in any order and may be restricted to those variables to be changed.

Note: The state-qualified, time/event qualified and pattern trigger types use the trigger pattern defined by the command TRIG-GER_PATTERN.

The TRIG_SELECT? query returns the current trigger condition.

Trigger Notation

STD	Standard	SNG	Single source
PA	Pattern	SQ	State qualified
TEQ	Time event qualified	TI	Time
PL	Pulse larger	IL	Interval larger
ΕV	Event	PS	Pulse smaller
IS	Interval smaller	SR	Source
HT	Hold type	HV	Hold value

TV Trigger Notation

FLD	Field	FLDC	Field Count
LINE	Line	CHAR	Characteristics
I PIC	Lines per picture	ILAC	Interlace

SR does not apply to the Pattern trigger. HT and HV do not apply to the standard trigger.

COMMAND SYNTAX

<trig_type> := {STD, SNG, SQ, TEQ, PA} <source> := {C1, C2, LINE, EX&, C4‡} <hold_type> := {TI, EV, PS, PL, IS, IL} <hold_value> := 25NS to 20S for TI 1 to 109 for EV

‡ standard 9424 only, & 9424 with ext. trigger option only

2.5NS to 20S for PS and PL* 10NS to 20S for IS* 25NS to 20S for IL*

* these values are only valid for single-source and pattern triggers.

Note: The suffix S (seconds) is optional.

COMMAND SYNTAX

TV TRIGGER

TRig_SElect TV,SR,C3,FLDC,<field_count>,FLD,<field>, CHAR, <characteristics>, LPIC@, <lpic>, ILAC@, <ilace>, LINE, <line>

<field_count> := {1, 2, 4, 8} <field> := 1 to field_count

<characteristics> := { NTSC,PALSEC,CUST50&,CUST60&}

<|pic> := 1 to 1500<ilace> := $\{1, 2, 4, 8\}$ < line > := 1 to 1500

Note: The FLD value is interpreted with the current FLDC value. The LINE value is interpreted with the current FLD and CHAR values.

QUERY SYNTAX

TRig_SElect?

Response format

TRig_SElect <trig_type>,SR,<source>,HT,<hold_type>,

HV,<hold value>

TRig_SElect TV,SR,C3,FLDC,<field_count>,FLD,<field>,

CHAR, < characteristic>, LINE, < line>

EXAMPLE (GPIB)

The following command selects the single-source trigger with Channel 1 as trigger source. Hold type and hold value are chosen

as "Pulse smaller" than 20 µsec

CMD\$="TRSE SNG,SR,C1,HT,PS,HV,20 US"

CALL IBWRT(SCOPE%, CMD\$)

EXAMPLE: TV

CMD\$ = "TRSE TV,SR,C3,FLDC,8,FLD,3,CHAR,

PALSEC, LINE, 17"

RELATED COMMANDS

TRIG COUPLING, TRIG LEVEL, TRIG MODE, TRIG PAT-

TERN, TRIG SLOPE

[@] for CUST50 and CUST60 only, & for oscilloscopes with HDTV hardware option only

TRIG_SLOPE, TRSL

Command/Query

DESCRIPTION

The TRIG_SLOPE command sets the trigger slope of the specified trigger source. An environment error (see Table 6, page 82) will be generated when TRSL NEG is received while the trigger coupling is set to HFDIV (see TRIG_COUPLING).

The TRIG_SLOPE? query returns the trigger slope of the selected

source.

COMMAND SYNTAX

<trig_source>:TRig_SLope <trig_slope>

 $\langle \text{trig_source} \rangle := \{\text{C1, C2, EX}^{\&}, \text{EX}^{10}^{\dagger}, \text{C4}^{\ddagger}\}$

<trig_slope> := {NEG, POS}

QUERY SYNTAX

<trig_source>:TRig_SLope?

Response format

<trig_source>:TRig_SLope <trig_slope>

EXAMPLE (GPIB)

The following command sets the trigger slope of Channel 2 to

negative.

CMD\$="C2:TRSL NEG": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

TRIG_SELECT

[‡] standard 9424 only, † 9420/50 only, & 9424 with ext. trigger option

MISCELLANEOUS

*TST?

Query

DESCRIPTION

The *TST? query performs an internal self-test. The response indicates if the self-test detected any errors. The self-test includes testing the hardware of all channels, the time base and the trigger circuits.

Hardware failures are identified by a unique binary code in the returned <status> number (see Table 1, page 46). A "0" response indicates that no failures occurred.

Note: This query is only accepted in remote mode.

QUERY SYNTAX

*TST?

Response Format

*TST <status>

<status>:= 0 self-test successful

EXAMPLE (GPIB)

This example causes a self-test to be performed.

CMD\$="*TST?": CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%,RD\$): PRINT RD\$

Response message (if no failure)

*TST 0

RELATED COMMANDS

*CAL?

STATUS

URR?

Query

DESCRIPTION

The URR? query reads and clears the contents of the User Request status Register (URR). The URR register specifies which button in the menu field was pressed. Refer to Table 9 for further details.

In the remote mode, the URR register indicates the last button (2 ... 10) which was pressed. In local mode, the URR register indicates whether the CALL HOST button has been pressed. If no menu button has been pressed since the last URR? query, the value 0 is returned. Figure 1, (page NO TAG) shows the button assignments on the instrument.

QUERY SYNTAX

URR?

Response format

URR <value>

<value> := 0 to 9, 100

EXAMPLE (GPIB)

The following instruction reads the contents of the URR register.

CMD\$="URR?": CALL IBWRT(SCOPE%,CMD\$) CALL IBRD(SCOPE%,RSP\$): PRINT RSP\$

Response message

URR 0

RELATED COMMANDS

CALL_HOST, KEY, ALL STATUS?, *CLS

Value	Description
0 1 2 3 4 5 6 7	no button has been pressed button 1 has been pressed. button 2 has been pressed. button 3 has been pressed. button 4 has been pressed. button 5 has been pressed. button 6 has been pressed. button 7 has been pressed.
8 9 100	button 8 has been pressed. button 9 has been pressed. The "Call Host" key (button 10 In root menu) has been pressed.

User Request Status Register Structure (URR)
Table 9

DISPLAY

VERT_MAGNIFY, VMAG

Command/Query

DESCRIPTION

The VERT MAGNIFY command vertically expands the specified trace. The command is executed even if the trace is not displayed. The VERT_MAGNIFY? query returns the magnification factor of

the specified trace.

COMMAND SYNTAX

<trace>:Vert_MAGnify <factor>

<trace> := {EA, EB, MC, MD, FE, FF}

< factor > := 0.2 to 5.0 (10.0 for high resolution data)

QUERY SYNTAX

<trace>:Vert_MAGnify?

Response format

<trace>:Vert_MAGnify <factor>

EXAMPLE (GPIB)

The following command enlarges the vertical amplitude of Function E by a factor of 3.45 with respect to its original amplitude. CMD\$="FE:VMAG 3.45": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

VERT_POSITION

DISPLAY

VERT_POSITION, VPOS

Command/Query

DESCRIPTION

The VERT_POSITION command adjusts the vertical position of the specified trace on the screen. The VERT_POSITION command does not affect the original offset value obtained at acquisition time.

acquisition time.

The VERT_POSITION? query returns the current vertical posi-

tion of the specified trace.

COMMAND SYNTAX

<trace>:Vert_POSition <display_offset>

<trace> := {EA, EB, MC, MD, FE, FF} <display_offset> := -56 DIV to 56 DIV

Note: The suffix DIV is optional.

QUERY SYNTAX

<trace>:Vert_POSition?

Response format

<trace>:Vert_POSition <display_offset>

EXAMPLE (GPIB)

The following command shifts Expand A (EA) upwards by +3 divisions, relative to the position at the time of acquisition.

CMD\$="EA:VPOS 3DIV": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

VERT_MAGNIFY

ACQUISITION

VOLT DIV, VDIV

Command/Query

DESCRIPTION

The VOLT_DIV command sets the vertical sensitivity in Volts/div. Values ranging between 5.0 mV and 2.5 V can be specified. The VAB bit (bit 2) in the STB register (Table 8, page 121) is set if an out-of-range value is entered.

Note: The probe attenuation factor is not taken into account for adjusting vertical sensitivity.

The VOLT_DIV? query returns the vertical sensitivity of the specified channel.

COMMAND SYNTAX

<channel>:Volt_DIV <v_gain>

<channel> := {C1, C2, C3‡, C4‡}

 $\langle v_gain \rangle := 5.0 \text{ mV to } 2.5 \text{ V}$

Note: The suffix V is optional.

QUERY SYNTAX

<channel>:Volt_DIV?

Response format

<channel>:Volt_DIV <v_gain>

EXAMPLE (GPIB)

The following command sets the vertical sensitivity of channel 1 to

50 mV/div.

CMD\$="C1:VDIV 50MV": CALL IBWRT(SCOPE%,CMD\$) **STATUS**

*WAI

Command

DESCRIPTION

The *WAI (WAIt to continue) command, required by the IEEE 488.2 standard, has no effect on the oscilloscope as the oscilloscope only starts processing a command when the previous command has been entirely executed.

Note: This command can be executed in both local and remote modes.

Command syntax

*WAI

RELATED COMMANDS

*OPC

ACQUISITION

WAIT

Command

DESCRIPTION

The WAIT command prevents the instrument from analyzing new commands until the oscilloscope has completed the current acquisition process.

COMMAND SYNTAX

WAIT

EXAMPLE

```
send: "TRMD SINGLE"
loop {send: "ARM; WAIT;C1:PAVA? MAX"
read response
process response
```

This example finds the maximum amplitudes of several signals acquired one after another. ARM starts a new data acquisition. The WAIT command ensures that the maximum is evaluated for the newly acquired waveform.

"C1:PAVA? MAX" instructs the instrument to evaluate the maximum data value in the channel 1 waveform.

WAVEFORM TRANSFER

WAVEFORM. WF

Command/Query

DESCRIPTION

A WAVEFORM? query transfers a waveform from the oscilloscope to the controller, whereas a WAVEFORM command transfers a waveform from the controller to the oscilloscope.

The WAVEFORM command stores an external waveform back into the oscilloscope's internal memory. A waveform consists of several distinct entities:

- (1) the descriptor (DESC),
- (2) the user text (TEXT),
- (3) the time (TIME) descriptor,
- (4) the data (DAT1) block, and optionally
- (5) a second block of data (DAT2).

For further information on the structure of the waveform refer to Section 6. In the 9424 the WAVEFORM command automatically sets the corresponding function to the memory state.

Note: Only complete waveforms queried with "WAVEFORM? ALL" can be restored into the oscilloscope.

The WAVEFORM? query instructs the oscilloscope to transmit a waveform to the controller. The entities may be queried independently. If the "ALL" parameter is specified, all 4 or 5 entities are transmitted in one block in the order enumerated above.

Note: The format of the waveform data depends on the current settings specified by the last WAVEFORM_SETUP command, the last COMM_ORDER command and the last COMM_FORMAT command.

COMMAND SYNTAX

<memory>:WaveForm ALL,<waveform_data_block>

<memory>:= {MC, MD, FE‡, FF‡}

<waveform_data_block> := arbitrary data block

QUERY SYNTAX

<trace>:WaveForm? <block>

<trace>:= {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}

<block>:= {DESC, TEXT, TIME, DAT1, DAT2, ALL}

Note: If no parameter is given ALL will be assumed.

Response format

<trace>:WaveForm <block>,<waveform data block>

‡ 9424 only

Note: It may be convenient to disable the response header if the waveform is to be restored. Refer to command COMM_HEADER for further details.

EXAMPLE (GPIB)

1) The following command reads the block DAT1 from Memory C and saves it in the file "MEMC.DAT". The path header "MC:" is saved together with the data.

FILE\$ = "MEMC.DAT"

CMD\$ = "MC:WF? DAT1"

CALL IBWRT(SCOPE%,CMD\$)

CALL IBRDF(SCOPE%,FILE\$)

2) In the following example, the entire contents of Channel 1 are saved in the file "CHAN1.DAT". The path header "C1:" is skipped to ensure that the data can later be recalled into the oscilloscope.

FILE\$ = "CHAN1.DAT":RD\$=SPACE\$(3)

CMD\$ = "CHDR SHORT; C1:WF?"

CALL IBWRT(SCOPE%,CMD\$)

CALL IBRD(SCOPE%,RD\$) Skip first 3 characters "C1:"

CALL IBRDF(SCOPE%,FILE\$) Save data in the file

"CHAN1.DAT"

3) The following example illustrates how the waveform data saved in example 2) can be recalled into Memory C.

FILE\$ = "CHAN1.DAT"

CMD\$ = MC:TRACE ON"

CALL IBWRT(SCOPE%,CMD\$)

CALL IBWRTF(SCOPE%,FILE\$)

The MC:TRACE ON command ensures that the <trace> is set to "MC". When the data file is sent to the instrument, it first sees the header "WF" (the characters "C1:" having been skipped when reading the file) and assumes the default destination "MC".

RELATED COMMANDS

INSPECT?, COMM_FORMAT, COMM-ORDER, FUNCTION_STATE‡, TEMPLATE?, WAVEFORM_SETUP, WAVEFORM_TEXT,

WAVEFORM TRANSFER

WAVEFORM_SETUP, WFSU

Command/Query

DESCRIPTION

The WAVEFORM_SETUP command specifies the amount of data in a waveform which will be transmitted to the controller. The command controls the settings of the following parameters:

a. Sparsing (SP). The sparsing parameter defines the interval (0..25000) between data points. For example:

SP = 0 reads all data points

SP = 1 reads all data points

SP = 4 reads every 4th data point

b. Number of points (NP). The number of points parameter indicates how many points should be transmitted. For example:

NP = 0 sends all data points

NP = 1 sends 1 data point

NP = 5 sends a maximum of 5 data points

NP = 10 sends a maximum of 10 data points

NP = 50 000 sends a maximum of 50 000 data points

c. First point (FP). The first point parameter specifies the address of the first data point to be sent. For waveforms acquired in sequence mode, this refers to the relative address in the given segment. For example:

FP = 0 corresponds to the first data point

FP = 1 corresponds to the second data point

FP = 5000 corresponds to data point 5001

d. Segment number (SN). The segment number parameter (0 to 200) indicates which segment should be sent if the waveform was acquired in sequence mode. This parameter is ignored for non-segmented waveforms. For example:

SN = 0 all segments

SN = 1 first segment

SN = 23 segment 23

The WAVEFORM_SETUP? query returns the transfer parameters currently in use.

Notation

SP sparsing NP number of points FP first point SN segment number

COMMAND SYNTAX

WaveForm_SetUp SP,<sparsing>,NP,<number>,FP,<point>,

SN, < segment>

<sparsing> := 0 to 25000 (0 = no sparsing)<number> := 0 to 50000 (0 = all data points)

<point> := 0 to 50000

 $\langle segment \rangle := 0 \text{ to } 200$ (0 = all segments)

Note 1: After power-on, all values are set to 0 (i.e. entire wave-

forms will be transmitted without sparsing).

Note 2: Parameters are grouped in pairs. The first one names the variable to be modified and the second one gives the new value to be assigned. Pairs may be given in any order and may be restricted to those variables to be changed.

QUERY SYNTAX

WaveForm_SetUp?

Response format

WaveForm_SetUp SP,<sparsing>, NP,<number>,

FP,<point>,SN,<segment>

EXAMPLE (GPIB)

The following command specifies that every 3rd data point (SP=3)

starting at address 200 should be transferred.

CMD\$="WFSU SP,3,FP,200" CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

INSPECT?, WAVEFORM, TEMPLATE

WAVEFORM TRANSFER

WAVEFORM_TEXT, WFTX

Command/Query

DESCRIPTION

The WAVEFORM_TEXT command is used to document the conditions under which a waveform has been acquired. The text

buffer is limited to 400 characters.

The WAVEFORM_TEXT? query returns the text section of the

specified trace.

COMMAND SYNTAX

<trace>:WaveForm TeXt '<text>'

<trace> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}

<text> := An ASCII message (max. 400 characters long)

QUERY SYNTAX

<trace>:WaveForm TeXt?

Response format

<trace>:WaveForm_TeXt "<text>"

EXAMPLE (GPIB)

The following example shows how to document Function E (FE).

MSG\$ = "'Averaged pressure signal.

Experiment carried out Oct. 15, 88""

CMD\$ = "FE:WFTX "+ MSG\$ CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

INSPECT?, WAVEFORM, TEMPLATE?

DISPLAY

XY_ASSIGN, XYAS

Command/Query

DESCRIPTION

The XY ASSIGN command assigns traces to the X and Y axis to create an X versus Y display.

The XY_ASSIGN? query returns the traces currently assigned to the XY display. If there is no trace assigned to the X-axis and/or the Y-axis the value UNDEF will be returned instead of the trace name.

COMMAND SYNTAX

XY_ASsign <X_source>,<Y_source>

<X source> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡} <Y_source> := {EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}

QUERY SYNTAX

XY_ASsign?

Response Format

XY_ASsign <X_source>,<Y_source>

<X_source> := {UNDEF, EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}

<Y_source> := {UNDEF, EA, EB, MC, MD, FE, FF, C1, C2, C3‡, C4‡}

EXAMPLE (GPIB)

The following command will assign Channel 1 to X and Channel 2

to Y.

CMDS\$="XYAS C1,C2": CALL IBWRT(SCOPE%,CMDS\$)

CURSOR

XY_CURSOR_ORIGIN, XYCO

Command/Query

DESCRIPTION

The XY_CURSOR_ORIGIN command sets the position of the origin for absolute time cursor measurements on the XY display.

Absolute time cursor values may be measured either with respect to the point (0,0) volts (OFF) or with respect to the center of the

XY grid (ON).

The XY_CURSOR_ORIGIN query returns the current assignment of the origin for absolute time cursor measurements.

COMMAND SYNTAX

XY_Cursor_Origin <mode>

 $< mode > := \{ON, OFF\}$

QUERY SYNTAX

XY_Cursor_Origin?

Response Format

XY_Cursor_Origin <mode>

EXAMPLE (GPIB)

The following command sets the origin for absolute time cursor

measurements to the center of the XY grid.

CMDS\$="XYCO ON": CALL IBWRT(SCOPE%,CMDS\$)

CURSOR

XY_CURSOR_SET, XYCS

Command/Query

DESCRIPTION

The XY_CURSOR_SET command allows the user to position any one of the nine independent XY cursors at a given screen location. The positions of the cursors can be modified or queried even if the required cursor is not currently displayed or if the XY display mode is OFF.

The XY_CURSOR_SET? query indicates the current position of the cursor(s). The values returned are quoted relative to the original waveform (time or frequency domain).

Notation	
HABS	Horizontal absolute
HREF	Horizontal reference
HDIF	Horizontal difference
XABS	Vertical absolute on X axis
XREF	Vertical reference on X axis
XDIF	Vertical difference on X axis
YABS	Vertical absolute on Y axis
YREF	Vertical reference on Y axis
YDIF	Vertical difference on Y axis

COMMAND SYNTAX

XY_Cursor_Set <cursor>,<position>

[<cursor>,<position><cursor>,<position>]

<cursor> := {HABS, HREF,HDIF, XABS, XREF,XDIF, YABS, YREF, YDIF}

<position> := 0 to 10 DIV (horizontal)

- 4 to 4 DIV (vertical)

Note 1: The suffix DIV is optional.

Note 2: Parameters are grouped in pairs. The first one names the cursor to be modified and the second one indicates its new value. Pairs may be given in any order and may be restricted to those items to be changed.

QUERY SYNTAX XY_Cursor_Set? [<cursor,...<cursor>]

<cursor> := {HABS, HREF, HDIF, XABS, XREF, XDIF, YABS,

YREF, YDIF, ALL}

Note: If <cursor> is not specified, ALL will be assumed.

Response Format XY_Cursor_Set <cursor>,<position>[<cursor>,<position>...

...,<cursor>,<position>]

EXAMPLE (GPIB) The following command positions the XREF and YDIF at +3 DIV

and -2 DIV respectively.

CMDS\$="XYCS XREF,3DIV,YDIF,-2DIV"

CALL IBWRT(SCOPE%,CMDS\$)

CURSOR

XY_CURSOR_VALUE, XYCV

Command/Query

DESCRIPTION

The XY CURSOR VALUE? query returns the current values of the X versus Y trace parameters. The X versus Y trace does not need to be displayed to obtain these parameters, but valid sources must be assigned to the X and Y axes.

Parameter Names

<cursor type> X X

Y <cursor type> Y

<cursor type>_RATIO $\Delta Y/\Delta X$

<cursor type> PROD $\Delta Y * \Delta X$

<cursor type>_ANGLE arc tan($\Delta Y/\Delta X$)

<cursor type> RADIUS $sqrt(\Delta X^*\Delta X + \Delta Y^*\Delta Y)$

<cursor type> := [HABS, HREL, VABS, VREL]

QUERY SYNTAX

XY Cursor_Value? [<parameter>,...<parameter>]

<parameter> := {HABS X, HABS Y, HABS RATIO, HABS_PROD, HABS_ANGLE, HABS_RADIUS, HREL_X, HREL Y, HREL RATIO, HREL PROD, HREL ANGLE, HREL_RADIUS, VABS_X, VABS_Y, VABS_RATIO, VABS PROD, VABS ANGLE, VABS RADIUS, VREL X, VREL_Y, VREL_RATIO, VREL_PROD, VREL_ANGLE, VREL_RADIUS, ALL}

Note: If <parameter> is not specified or equals ALL, all the measured cursor values are returned. If the value of a cursor could not be determined in the current environment, the value UNDEF will be returned.

Response Format

XY_Cursor_Value <parameter>,<value>

[....<parameter>,<value>]

<value> := decimal value or UNDEF

EXAMPLE (GPIB)

The following query reads the ratio of the absolute horizontal cursor, the angle of the relative horizontal cursor and the product of the absolute vertical cursor.

CMDS\$="XYCV?HABS RATIO,HREL ANGLE,VABS PROD CALL IBWRT(SCOPE%, CMDS\$)

DISPLAY

XY_DISPLAY, XYDS

Command/Query

DESCRIPTION

The XY_DISPLAY command enables or disables the XY display

mode.

The XY_DISPLAY? query returns the current mode of the XY

display.

COMMAND SYNTAX

XY_DiSplay <mode>

<mode $> := {ON, OFF}$

QUERY SYNTAX

XY_DiSplay?

Response Format

XY_DiSplay <mode>

EXAMPLE (GPIB)

The following command turns the XY display ON.

CMDS\$="XYDS ON": CALL IBWRT(SCOPE%,CMDS\$)

DISPLAY

ZOOM

Command/Query

DESCRIPTION

The ZOOM command allows the user to select which trace is to be

expanded by one of the expansion functions.

The response to the ZOOM? query indicates which trace is cur-

rently expanded.

In the 9424 the ZOOM command automatically switches the func-

tion to the expand state

COMMAND SYNTAX

<exp_trace>:ZOOM <trace>

<exp_trace> := {EA, EB, MC‡, MD‡}
<trace> := {MC, MD, FE, FF, C1, C2, C3‡, C4‡}

QUERY SYNTAX

<exp_trace>:ZOOM?

Response format

<exp_trace>:ZOOM <trace>

EXAMPLE (GPIB)

The following example selects Memory C (MC) as the source for

Expand B (EB).

CMD\$="EB:ZOOM MC": CALL IBWRT(SCOPE%,CMD\$)

RELATED COMMANDS

DUAL ZOOM

		Street, Walleton
		Branches "Comm
		Manager agent account.
		D. Aller State Sta
		The second secon
		n-Ja [*] Ammonin surveni
		noninamina and associate
		de el manuela de el
		eren ger vijeks (in s
		abilities and plants
		Approximate 1 v v v
		The second secon
		AND
		1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1
		Topong Priprint
		aprobabas en re-

WAVEFORM STRUCTURE

INTRODUCTION

This section discusses how to read and write waveforms and understand their contents. Waveforms can be divided into two basic entities, the basic data array (i.e. the raw data values from the ADC's in the acquisition) and the accompanying descriptive information, such as vertical scale, horizontal scale, time of day which are necessary for a full understanding of the data.

The information in a waveform can be accessed using the IN-SPECT? command which interprets it in an easily understood ASCII text form. It can also be more rapidly transferred using the WAVEFORM? command or written back into the instrument with the WAVEFORM command. The oscilloscope contains a data structure called the template which is a detailed description of how the waveform's information is organized.

LOGICAL DATA BLOCKS OF A WAVEFORM

The template gives a detailed description of the form and contents of the logical data blocks of a waveform. It is provided as a reference to be used by you and your programs. A sample template is given in Appendix B although you are encouraged to use the TEMPLATE? command to examine the actual template that your instrument is using. The template may change as the instrument's firmware is enhanced. The template will help provide backward compatibility for the interpretation of waveforms.

Usually, a waveform will contain just a Waveform descriptor block (1.) and a Data array block (5.). In more complicated cases one or more of the other blocks will be present. The data blocks are:

- 1. Waveform descriptor block (WAVEDESC). This block includes all the information necessary to reconstitute the display of the waveform from the data. This includes:
 - · hardware settings at the time of acquisition
 - · the exact time of the event
 - · the kinds of processing that have been performed
 - the name and serial number of the instrument
 - the encoding format used for the data blocks
 - · miscellaneous constants
- 2. An optional user-provided text (USERTEXT). The WFTX command can be used to put a title or description of a waveform into this block. The WFTX? query command gives an alternative way to read it. This text block can hold up to 400 characters. However, you should limit the length of each line to about 45 characters, otherwise the text will be wrapped onto the next line after 56 characters.
- 3. A block of sequence acquisition times (TRIGTIME). This block is needed for sequence acquisitions to record the exact

timing information for each segment. It contains the time of each trigger relative to the trigger of the first segment, as well as the time of the first data point of each segment relative to its trigger.

- 4. A block of random interleaved sampling times (RISTIME). This block is needed for RIS acquisitions to record the exact timing information for each segment.
- 5. A data array block (SIMPLE or DATA_ARRAY_1). This is the basic integer data of the waveform. It can be raw or corrected ADC data or the integer result of waveform processing.
- 6. A second data array block (DATA_ARRAY_2). This second data array is needed to hold the results of processing functions such as the Extrema (WP01 option) or Complex FFT (WP02 option). In such cases, the data arrays contain:

	Extrema	FFT
DATA_ARRAY_1	Roof trace	Real part
DATA_ARRAY_2	Floor trace	Imaginary part

Note: The TEMPLATE also describes an array named DUAL. This is simply a way to allow the INSPECT? command to examine the two data arrays together.

INSPECT? COMMAND

This is the simplest way to examine the contents of a waveform. It can be used on both the data and descriptive parts. The simplest form of the command is:

INSPECT? "name"

where the template gives the name of a descriptor item or data block. The answer is returned as a single string, but may span many lines. Here is some typical dialogue:

The INSPECT? command can also be used to get a readable translation of the full waveform descriptor block with the command:

```
INSPECT? "WAVEDESC"
```

The template dump from your instrument (or from Appendix B) will give details on the interpretation of each of the parameters.

The INSPECT? command is also used to examine the measured data values of a waveform. For an acquisition with 42 points we get:

INSPECT? "SIMPLE" C1:INSP "

4.68749e-03	1.09375e-02	1.71875e-02	2.03125e-02	2.03125e-02	2.65625e-02
3.28125e-02	3.59375e-02	3.90625e-02	4.53125e-02	5.15625e-02	5.15625e-02
5.78125e-02	6.40625e-02	6.71875e-02	6.71875e-02	7.65625e-02	7.96875e-02
8.59375e-02	8.90625e-02	9.21875e-02	9.53125e-02	1.04687e-01	1.04687e-01
1.07812e-01	1.14062e-01	1.20312e-01	1.20312e-01	1.26562e-01	1.29688e-01
1.32812e-01	1.39062e-01	1.42187e-01	1.51562e-01	1.54687e-01	1.57812e-01
1.60938e-01	1.60938e-01	1.70312e-01	1.73437e-01	1.70312e-01	1.76563e-01
19					

These numbers are the fully converted measurements in volts. Of course, when the data block contains thousands of items the string will contain many lines.

Depending on the application, you may prefer to have the data in its raw form as either a BYTE (8 bits) or a WORD (16 bits) for each data value. In this case you must use the relations given below in association with the WAVEFORM? command to interpret the measurement. The command might then say:

INSPECT? "SIMPLE", BYTE

The examination of data values for waveforms with two data arrays can be done as follows:

INSPECT? "DUAL" to get pairs of data values on a single line INSPECT? "DATA_ARRAY_1"

to get the values of the first data array

INSPECT? "DATA_ARRAY_2"

to get the values of the second data array

It is also possible to examine just a part of the waveform or a sparsed form of the waveform. This is controlled with the WAVE-FORM_SETUP command mentioned later in this section.

The INSPECT? command has only a query form. It cannot be used to send a waveform back into the oscilloscope. It is also a very verbose way in which to send the information and is not very fast. Users who need speed or the ability to send the waveform back to the instrument should use the WAVEFORM commands.

BASIC users might find it convenient to combine the capabilities of the inspect facility with the waveform query command in order to construct files containing a human and BASIC readable version of the waveform descriptor together with the full waveform in a format suitable for retransmission to the instrument. This can be



done for a waveform in a memory location by sending the com-

MC:INSPECT? "WAVEDESC"; WAVEFORM?

and putting the response directly into a disk file.

WAVEFORM? COMMAND

The WAVEFORM commands are an efficient way to transfer waveform data using the block formats defined in the IEEE-488.2 standard. You have the possibility of reading all of the logical blocks of the waveform with a single query:

C1:WAVEFORM?

This is the preferred form for most applications since it is complete and the response can be downloaded back into the instrument using the WAVEFORM command. You can also choose to read any single block with a query like:

C1:WAVEFORM? DAT1

This can save time and space when you need to read many waveforms all with the same acquisition conditions or if you are only interested in lots of raw integer data. Consult the description of the WAVEFORM command in Section 5 for the names of the various blocks.

Please be aware that a waveform query response can easily be a block containing over 200,000 bytes if it is in binary format and twice as much if the HEX option is used.

Interpreting the waveform descriptor

The binary response to a query command of the form:

C1:WAVEFORM? or C1:WAVEFORM? ALL

can be put into a disk file and then dumped to show the following hexadecimal and ASCII form: (This was done over GPIB with default settings)

Byte offset	Bina	ry cor	ntents	in he	exade	cimal			ASCII translation (b is for uninteresting)
0			4620						C1:WF ALL, #90000
16			3057						00430WAVEDESCbbb
32			004c						bbbbbLECROY_1_1b
48			0000						bbbbbbbbbbbbbb
64			0000						bbbbbbbbbbbbbb
80			5400						bbbbbbbbbbbbbbb
96			524f						bLECROY9450_bbbb
112			b100						• • •
128			0000						
144			0000						
160			0000						
176			cd3a						
192			0031						
208			8ee0						
224			0000						
240			0000						
256			0000					-	
272	0000	0000	0000	0 000	0000	0000	0000	0000	
288			0000						
304			0000						
320			0004						
336			0000						
352			003f						
368			0007						
384			0011						
400			0 01d						
416			0027						
432 448		0032 000a	0033	0034	0034	0037	0038	0037	
440	0039	Jour							

It can be seen that the first 10 bytes translate into ASCII and look like the simple beginning of a query response. This is followed by the string "#9000000430". This is the beginning of a binary block where 9 ASCII integers are used to give the length of the block (430 bytes). The waveform itself starts immediately after this at byte number 21 (the first byte is byte 0).

Deciphering the waveform descriptor can be done with the aid of the template (see Appendix B). It states that the first object is a DESCRIPTOR_NAME which is a string of 16 characters with the value WAVEDESC and this is what we see. At byte 16 relative to the beginning of the descriptor (or byte 37 above) we find the next string, the TEMPLATE_NAME with the value LECROY_1_1. Several other parameters follow. We can easily recognize the IN-



STRUMENT NAME at 76 bytes from the descriptor start (or byte 97 above).

In a similar way we learn that a 4 byte long integer giving the length of the descriptor starts at byte 36 (or byte 57 above):

 $WAVE_DESCRIPTOR = 15a (hex) = 346$

At byte 60 (or byte 81 above) we find another 4 byte integer giving the length of the data array:

WAVE ARRAY 1 = 54 (hex) = 84

and at byte 116 (or byte 137 above) the number of data points:

 $WAVE_ARRAY_COUNT = 2a (hex) = 42$

Now we know that the data will start at byte 346 from the beginning of the descriptor (or byte 367 above) and that each of the 42 data points will be represented by two bytes. The waveform has a total length of 346 + 84 which is the same as the ASCII string told us at the beginning of the block. The final 0a at byte 451 is the NL character associated with the GPIB message terminator <NL><EOI>.

The data can be easily seen starting at byte 367 above. Since the oscilloscope has an 8 bit ADC we see those 8 bits followed by a 0 byte for each data point. It should be noted that for many other kinds of waveform this second byte will not be zero and contains interesting information. The data is coded in signed form (two's complement) with values ranging from -32768 = 8000 (hex) to 32767 = 7fff (hex). If we had chosen to use the BYTE option for the data format the values would have been signed integers in the range -128 = 80 (hex) to 127 = 7f (hex).

Interpreting the waveform vertical data

Now that we know how to decipher the data it would be useful to convert it to the appropriate measured values. The vertical reading for each data point depends on the vertical gain and the vertical offset given in the descriptor. For acquisition waveforms this corresponds to the volts/div and voltage offset selected after conversion for the data representation being used. The template tells us that the vertical gain and offset can be found at bytes 156 and 160 respectively of the descriptor and that they are stored as floating point numbers in the IEEE 32 bit format. An ASCII string giving the vertical unit is to be found in VERTUNIT, byte 196. The vertical value is given by the relationship:

value = VERTICAL_GAIN * data - VERTICAL_OFFSET

A data value of 0 is normally displayed as a point in the middle of the grid.

In the case of the data shown above we find:

= 1.22070314e-05 from the floating VERTICAL_GAIN point number 374c cccd at byte 177

VERTICAL_OFFSET = 1.56250596e-03 from the floating

point number 3acc cd00 at byte 181

VERTICAL_UNIT = V = volts from the string 5600 ... at byte 217

and therefore:

since data[0] = 512 from the hexadecimal word 0200 at byte

value[0] = 0.00468 V as stated in the inspect command

above

and

since data[1] = 1024 from the hexadecimal word 0400 at byte

369

= 0.0109 V as stated in the inspect command value[0]

above.

If your computer or available software is incapable of understanding the IEEE floating point values you can find a description of this format in the template (see Appendix B).

The data values in a waveform may not all correspond to measured points. The parameters, FIRST_VALID_PNT and LAST_VAL-ID PNT give the necessary information. The descriptor also records the SPARSING_FACTOR, the FIRST_POINT, and the SEGMENT_INDEX to aid interpretation if the options of the WAVEFORM_SETUP command have been used.

For sequence acquisitions the data values for each segment are given in their normal order and the segments are read out one after the other. The important descriptor parameters are the WAVE_ARRAY_COUNT and the SUBARRAY_COUNT, giving the total number of points and the number of segments.

For waveforms such as the extrema and the complex FFT there will be two arrays one after the other for the two arrays of the result.

Calculating the horizontal position of a data point

Each vertical data value has a corresponding horizontal position, usually measured in time or in frequency units. The calculation of this position depends on the type of waveform being examined. We will treat separately the single sweep, the sequence, and the interleaved (RIS) waveform. Each data value has a position, i, in 6

the original waveform with i=0 corresponding to the first data point acquired. The descriptor parameter HORUNIT gives a string with the name of the horizontal unit.

• Single-sweep waveforms

For acquisition waveforms this time is from the trigger to the data point in question. It will be different from acquisition to acquisition since the HORIZ_OFFSET is measured for each trigger.

In the case of the data shown above this means:

HORIZ_INTERVAL = 2.5000e-09 from the floating point number 312b cc77 at byte 197

HORIZ_OFFSET = -1.21044098e-08 from the double precision floating point number be49 fe78

3be8 0000 at byte 201

HORUNIT = S = seconds from the string 5300 ... at byte

265

which gives

$$x[0] = -1.210e-08 S$$

 $x[1] = -0.960e-08 S$

Sequence waveforms

Since sequence waveforms are really many independent acquisitions, each segment will have its own horizontal offset. These can be found in the TRIGTIME array. For the n'th segment

The TRIGTIME array can contain up to 200 segments of timing information with two 8 byte double precision floating point numbers for each segment.

Interleaved (RIS) waveforms

These waveforms are composed of many acquisitions interleaved together. The descriptor parameter, SWEEPS_PER_ACQ gives the number of acquisitions. The i'th point will belong to the m'th segment where

m = i modulo (SWEEPS_PER_ACQ)

will have a value between 0 and SWEEPS_PER_ACQ - 1.

Then with

$$i = i - m$$

$$x[i] = x[j,m] = HORIZ_INTERVAL * j + RIS_OFFSET[m]$$

where the RIS_OFFSET's can be found in the RISTIME array. There can be up to 100 8 byte double precision floating point numbers in this block. The instrument tries to get segments with times such that

RIS_OFFSET[i] \approx PIXEL_OFFSET + (i - 0.5) * HORIZ_IN TERVAL

Thus, taking as an example a RIS with SWEEPS_PER_ACQ = 10 HORIZ_INTERVAL = 1 ns and PIXEL_OFFSET = 0.0, we might find for a particular event that:

```
RIS OFFSET[0] = -0.5 ns
                                        RIS OFFSET[1] = 0.4 \text{ ns}
RIS_OFFSET[2] = 1.6 \text{ ns}
                                        RIS_OFFSET[3] = 2.6 \text{ ns}
RIS OFFSET[4] = 3.4 \text{ ns}
                                        RIS OFFSET[5] = 4.5 \text{ ns}
RIS_OFFSET[6] = 5.6 \text{ ns}
                                        RIS_OFFSET[7] = 6.4 \text{ ns}
RIS_OFFSET[8] = 7.6 \text{ ns}
                                        RIS_OFFSET[9] = 8.5 \text{ ns}
and therefore:
x[0] = RIS_OFFSET[0]
                                        -0.5 ns
x[1] = RIS_OFFSET[1]
                                          0.4 \, \mathrm{ns}
                                  =
x[9] = RIS_OFFSET[9]
                                          8.5 ns
x[10] = 1 \text{ ns} * 10 + (-0.5) = 
x[11] = 1 \text{ ns} * 10 + 0.4 = 
                                         9.5 ns
                                         10.4 ns
x[19] = 1 \text{ ns } * 10 + 8.5
                                        18.5 ns
x[20] = 1 \text{ ns } * 20 + (-0.5) =
                                        19.5 ns
```

WAVEFORM COMMAND

Waveforms that have been read in their entirety with the WAVE-FORM? command can be sent back into the instrument. Since the descriptor contains all of the necessary information, you do not have to be careful about any of the communication format parameters. The instrument can learn all that it needs to know from the waveform.

If you want to synthesize waveforms for display or comparison purposes, you are encouraged to read out a waveform of the appropriate size and then replace the data with the desired values. This will assure that the descriptor is coherent.

Note: You are only allowed to send back waveforms to memory traces (MC or MD for 2-channel instruments or MC, MD, FE and FF for the 9424). This means that you may have to remove or change the prefix (C1 or CHANNEL_1) in the response to the WF? query. The examples for the WF command in Section 5 show how this can be done.



MORE CONTROL OF WAVEFORM QUERIES

There are many different ways for you to use the WAVEFORM? command which may simplify or speed up your work. Among them are:

Partial readout of waveform

The WAVEFORM_SETUP command allows you to specify a short part of a waveform for readout. It also lets you select a sparsing factor to read only every n'th data point.

Byte swapping

The COMM_ORDER command allows you to swap the two bytes of a 16-bit word. In fact, byte swapping is done for all numbers represented by more than one byte. This is the case for the descriptor, the time blocks, and WORD arrays, thereby simplifying data interpretation for some computer systems (e.g. INTEL based, or DEC)

• Data length, block format, and encoding

The COMM_FORMAT command gives you control over these parameters. If you do not need the extra precision of the lower order byte of the standard data value, the BYTE option lets you save a factor of two on the amount of data to be transmitted or stored. If your computer is not able to read binary data, the HEX option allows a response form where the value of each byte is given by a pair of hexadecimal digits.

• Data only transfers

The COMM_HEADER OFF mode will allow you to get a response to WF? DAT1 with the data only (the C1:WF DAT1 will disappear).

If you have also specified COMM_FORMAT OFF,BYTE,BIN, you will just get a response of data bytes (the #90000nnnnn will disappear).

Formatting for RS-232 users

The COMM_RS232 command can help you by splitting the very long WF? response into individual lines

HIGH-SPEED WAVEFORM TRANSFER

In order to achieve the maximum continuous data transfer rates from the oscilloscope to your instrument you will have to optimize many factors. The single most important point is to limit the work done in your computer. This means avoiding having to write the data to disk, minimizing the per data point computations, minimiz-

ing the number of calls to the IO system, etc. You can let the instrument help by reducing the number of points to be transferred and the number of data bytes per point. The pulse parameter capability and the processing functions can save you lots of computing and lots of data transfer time if employed creatively. Two other very important principles are:

- Try to overlap waveform acquisition with waveform transfer. The oscilloscope is capable of transferring an already acquired or processed waveform after a new acquisition has been started. This can also considerably increase the total time that the oscilloscope will be able to acquire events if it has to wait for triggers (livetime).
- Minimize the number of waveform transfers by using the sequence mode to accumulate many triggers for each transfer. This is preferable to using the WAVEFORM_SETUP command to reduce the number of data points to be transferred. It also reduces the oscilloscope transfer overhead significantly.

Here is an example of the type of commands to be given:

ARM to acquire the first event or sequence

WAIT; ARM; C1: WF? to wait for the event, start the next acquisition and then transfer the data.

This second line can be repeated by your program as soon as it has finished reading the waveform.

		Manager Manage
		Grand American
		elisin natara rolla
		Melitina _{Melitin} opp
		and the second
		n vicentificações
		Reacher Printing April
		disassing advances
		Anni Olimani e e delle
		- spanning Process
		many evidence has
		T QUA AL Inches to
		agencia à page
		· Canadan in
) in or ships
		OPPORTUGE.

STATUS REGISTERS

An extensive set of status registers allows the user to quickly determine the oscilloscope's internal processing status at any time. The status registers as well as the status reporting system have been designed to comply with IEEE 488.2 recommendations.

Related functions are grouped together in common status registers. Some, such as the Status Byte Register (STB) or the Standard Event Status Register (ESR), are required by the IEEE 488.2 standard. However, other registers are device specific. They include the Command Error Register (CMR) or the Execution Error Register (EXR). Commands associated with IEEE 488.2 mandatory status registers are preceded by an asterisk <*>.

OVERVIEW OF STATUS AND SERVICE REQUEST REPORTING


Figure 2 shows the organization of the 9420/24/50 status registers. The central reporting structure is the Status Byte Register (STB). It consists of 8 bits, three of which are not used.

The Standard Event Status Bit (ESB) and the Internal Status Change Bit (INB) in the Status Byte Register are summary bits of the Standard Event Status Register (ESR) and the Internal State Change Register (INR). The Message Available Bit (MAV) is set whenever there are data bytes in the output queue. The Value Adapted Bit (VAB) indicates that a parameter value was adapted during a previous command interpretation (e.g. if the command "TDIV 2.5 US" is received, the time base is set to 2 μ sec/div and the VAB bit is set).

The Master Summary Status bit (MSS) indicates that the instrument requests service. The MSS bit can only be set if any of the other bits of STB are enabled with the Service Request Enable Register (SRE).

All Enable registers (SRE, ESE and INE) are used to generate a bitwise AND with their associated status registers. The logical OR of this operation is reported to the STB register. At power-on, all Enable registers are zero, inhibiting any reporting to the STB.

The Standard Event Status Register (ESR) mostly summarizes errors, whereas the Internal State Change Register (INR) reports internal changes in the instrument. Additional details of the errors reported by ESR can be obtained with the queries "CMR?", "DDR?", "EXR?" and "URR?".



STATUS REGISTER STRUCTURE OF 9420/24/50 Figure 2

The register structure contains one more register (not shown in Figure 2). It is the Parallel Poll Enable Register (PRE) which acts exactly like the Service Request Enable Register (SRE), but it sets the "ist" bit (not shown in Figure 2), used in the Parallel Poll. The "ist" bit can also be read with the "*IST?" query.

Example of status reporting

If an erroneous remote command, e.g. "TRIG_MAKE SINGLE", is transmitted to the instrument, it rejects the command and sets the Command Error Register (CMR) to the value 1 (unrecognized command/query header). The non-zero value of CMR is reported to bit 5 of the Standard Event Status Register (ESR) which is then set.

Nothing further happens unless the corresponding bit 5 of the Standard Event Status Enable Register (ESE) is set (with the command "*ESE 32"), enabling the fact that bit 5 of ESR is set to be reported to the summary bit ESB of the Status Byte Register (STB).

If setting of the ESB summary bit in STB is enabled, again nothing happens unless further reporting is enabled by setting the corresponding bit in the Service Request Enable Register (with the command "*SRE 32"). In this case, the generation of a non-zero value of CMR ripples through to the Master Summary Status bit (MSS), generating a Service Request (SRQ).

The value of CMR can be read and simultaneously reset to zero at any time with the command "CMR?". The occurrence of a command error can also be detected by analyzing the response to "*ESR?". However, if several types of potential errors must be surveyed, it is usually much more efficient to enable propagation of the errors of interest into the STB with the enable registers ESE and INE.

Summary

A command error (CMR) sets bit 5 of ESR:

- if bit 5 of ESE is set, ESB of STB is also set.
- if bit 5 of SRE is set, MSS/RQS of STB is also set and a Service Request is generated.

STATUS BYTE REGISTER (STB)

The Status Byte Register is the instrument's central reporting structure. The STB is composed of 8 single-bit summary messages (of which 3 are unused) which reflect the current status of the associated data structures implemented in the instrument.

Bit 0 is the summary bit INB of the Internal State Change Register. It is set if any of the bits of the INR are set, provided that they are enabled by the corresponding bit of the INE register.

Bit 2 is the Value Adapted Bit, indicating that a parameter value was adapted during a previous command interpretation.

Bit 4 is the Message Available (MAV) bit, indicating that the interface output queue is not empty.

Bit 5 of STB is the summary bit ESB of the Standard Event Status Register. It is set if any of the bits of the ESR are set, provided that they are enabled by the corresponding bit of the ESE register.

Bit 6 of the Status Byte Register (STB) is alternatively called the Master Summary Status bit (MSS) or the Request for Service bit (RQS) because the STB can be read in two different ways. The command "*STB?" reads and clears the STB in the query mode in which case bit 6 of the STB is the MSS bit, indicating if the instrument has any reason for requesting service. The other way of reading the STB is the serial poll (see Section 3, page 22, for the GPIB serial poll procedure). In this case, bit 6 of the STB is the RQS bit, indicating the instrument has actually activated the SRQ line on the GPIB. The serial poll only clears the RQS bit. Therefore, the MSS bit of the STB (and any other bits which caused MSS to be set) will stay set after a serial poll. The controller must reset these bits.

The Status Byte Register may be read via the query "*STB?". The response represents the binary weighted sum of the register bits. The register is cleared by "*STB?", "ALST?", "*CLS" or after the instrument has been powered up.

STANDARD EVENT STATUS REGISTER (ESR)

The ESR is a 16-bit register reflecting the occurrence of events. The register bit assignments have been standardized by IEEE 488.2. Only the lower 8 bits are currently in use.

The Standard Event Status Register may be read via the query "*ESR?". The response is the binary weighted sum of the register bits. The register is cleared with an "*ESR?" or "ALST?" query, a "*CLS" command or after power-on.

Example

The response message "*ESR 160" indicates that a command error occurred and that the ESR is being read the first time after power-on. The value 160 can be broken down into 128 (bit 7) plus 32 (bit 5). See Table 5, page 80, for a description of the conditions corresponding to the bits set.

The "Power ON" bit appears only on the first "*ESR?" query after power—on because the query clears the register. The type of command error can be determined by reading the Command Error Status Register with the query "CMR?". Note that it is not necessary to read (and simultaneously clear) this register in order to be able to set the CMR bit in the ESR on the next command error.

STANDARD EVENT STATUS ENABLE REGISTER (ESE)

The ESE allows one or more events in the Standard Event Status Register to be reported to the ESB summary bit in the STB.

The Standard Event Enable Register is modified with the command "*ESE". It is cleared with the command "*ESE 0", or after power-on. It may be read with the query "*ESE?".

Example

"*ESE 4" sets bit 2 (i.e. binary 4) of the standard event enable register, enabling query errors to be reported.

SERVICE REQUEST ENABLE REGISTER (SRE)

The Service Request Enable Register specifies which summary bit(s) in the Status Byte Register will cause a service request. The Service Request Enable Register consists of 8 bits. Setting a bit in the register allows the summary bit located at the same bit position in the Status Byte Register to generate a service request provided that the associated event becomes true. Bit 6 (MSS) cannot be set and is always reported as zero in response to the query "*SRE?".

The Standard Event Enable Register is modified with the command "*SRE". It is cleared with the command "*SRE 0", or after power-on. It may be read with the query "*SRE?".

PARALLEL POLL ENABLE REGISTER (PRE)

The Parallel Poll Enable Register specifies which summary bit(s) in the Status Byte Register will set the "ist" individual local message. This register is quite similar to the Service Request Enable Register (SRE), but it is used to set the parallel poll "ist" bit rather than MSS.

The value of the "ist" may also be read without a Parallel Poll via the query "*IST?". The response indicates if the "ist" message has been set or not (values are 1 or 0).

The Parallel Poll Enable Register is modified with the command "*PRE". It is cleared with the command "*PRE 0", or after power-on. It may be read with the query "*PRE?". (See Section 3, page 23, for the GPIB parallel poll procedure.)

Example

"*PRE 5" sets bits 2 and 0 (decimal 4 and 1) of the Parallel Poll Enable Register.

INTERNAL STATE CHANGE

STATUS REGISTER (INR)

The INR reports the completion of a number of internal operations. The events tracked by this 16-bit-wide register are listed with the command "INR?" in Section 5.

The Internal State Change Status Register may be read via the query "INR?". The response is the binary weighted sum of the register bits. The register is cleared with an "INR?" or "ALST?" query, a "*CLS" command or after power-on.

INTERNAL STATE CHANGE

ENABLE REGISTER (INE)

The INE allows one or more events in the Internal State Change Status Register to be reported to the INB summary bit in the STB.

The Internal State Change Enable Register is modified with the command "INE". It is cleared with the command "INE 0", or after power-on. It may be read with the query "INE?".

COMMAND ERROR STATUS

REGISTER (CMR)

The Command Error Status register contains the code of the last command error detected by the instrument. Command error codes are listed with the command "CMR?" in Section 5.

The Command Error Status Register may be read via the query "CMR?". The response is the error code. The register is cleared with a "CMR?" or "ALST?" query, a "*CLS" command or after power-on.

DEVICE DEPENDENT ERROR STATUS REGISTER (DDR)

The DDR indicates the type of hardware errors affecting the instrument. Individual bits in this register report specific hardware failures. They are listed with the command "DDR?" in Section 5.

The Device Dependent Error Status Register may be read via the query "DDR?". The response is the binary weighted sum of the error bits. The register is cleared with a "DDR?" or "ALST?" query, a "*CLS" command or after power-on.

EXECUTION ERROR STATUS REGISTER (EXR)

The Execution Error Status Register contains the code of the last execution error detected by the instrument. Execution error codes are listed with the command "EXR?" in Section 5.

The Execution Error Status Register may be read via the query "EXR?". The response is the error code. The register is cleared with a "EXR?" or "ALST?" query, a "*CLS" command or after power-on.

USER REQUEST STATUS REGISTER (URR)

The URR contains the identification code of the last menu button which was pressed. The codes are listed with the command "URR?" in Section 5.

The User Request Status Register may be read via the query "URR?". The response is the decimal code associated with the selected menu button. The register is cleared with a "URR?" or "ALST?" query, a "*CLS" command or after power-on.

		Applications
		Water manufacture (), and deep
		*Augmente
		and the second second
		established in manufacture of the state of t
		egican men e verifica ana sistema distributione di
		distinguis, percentage of the second

APPENDIX A

EXAMPLE 1: USE OF THE INTERACTIVE

GPIB PROGRAM 'IBIC'

This example assumes the use of an IBM PC, or a compatible computer, equipped with a National Instruments GPIB interface card. It also assumes that the GPIB-driver is left in the default state so that the device name "dev4" corresponds to the GPIB address 4 which is assumed to be the address of the oscilloscope. All text entered by the user is underlined.

```
ibic<CR>
program announces itself
: ibfind<CR>
     enter board/device name: dev4<CR>
dev4: ibwrt<CR>
     enter string: "tdiv?" < CR>
[0100]
           (cmpl)
count: 5
dev4: ibrd<CR>
     enter byte count: 10<CR>
           (cmpl)
[0100]
count: 10
54 44 49 56 20 35 30 45
                                   TDIV
                                              5 0 E
2D 39
                                   - 9
dev4: ibwrt<CR>
     enter string: "c1:cpl?"<CR>
[0100]
           (cmpl)
count: 7
dev4: ibrd<CR>
     enter byte count: 20<CR>
[2100]
           (end cmpl)
count: 11
43 31 3A 43 50 4C 20 44
                                   C1:CPLD
35 30 0A
                                   5 0 ♦
dev4: a < CR >
     for quitting the program
```

EXAMPLE 2: GPIB PROGRAM FOR IBM PC (HIGH-LEVEL FUNCTION CALLS)

The following BASICA program allows full interactive control of the 9420/24/50 using an IBM PC as GPIB controller. It is again assumed that the controller is equipped with a National Instruments GPIB interface card. All the remote control commands listed in Section 5 can be used by simply entering the text string of the command, i.e. "c1:vdiv 50 mv" (without the quotes). The program automatically displays the information sent back by the oscilloscope in response to queries.

In addition, a few utilities have been provided for convenience. The commands ST and RC enable waveform data to be stored on or retrieved from disk if proper drive and file names are provided. The command LC returns the oscilloscope to local mode. Responses sent back by the oscilloscope are interpreted as character strings and are thus limited to a maximum of 255 characters.

Note 1: It is assumed that the National Instruments GPIB driver GPIB.COM is in its default state. This means that the interface board can be referred to by its symbolic name 'GPIB0' and that devices on the GPIB with addresses 1 to 16 can be called by the symbolic name 'DEV1' to 'DEV16'.

Note 2: Lines 1 – 99 are a copy of the file DECL.BAS supplied by National Instruments. The first 6 lines are required for the initialization of the GPIB handler. DECL.BAS requires access to the file BIB.M during the GPIB initialization. BIB.M is one of the files supplied by National Instruments, and must exist in the directory currently in use.

Note 3: The first 2 lines of DECL.BAS each contain a string "XXXXX" which must be replaced by the number of bytes which determine the maximum workspace for BASICA (computed by subtracting the size of BIB.M from the currently available space in BASICA). For example, if the size of BIB.M is 1200 bytes and when BASICA is loaded it reports "60200 bytes free", you would replace "XXXXX" by the value 59000 or less.

Note 4: The default timeout of 10 seconds is modified to 300 msec during the execution of this program. However, the default value of the GPIB handler is not changed. Whenever a remote command is entered by the user, the program sends it to the instrument with the function call IBWRT. Afterwards, it always executes an IBRD call, independently of whether or not a response is expected. If a response is received it is immediately displayed. If there is no response, the program waits until time-out and then asks for the next command.

```
1-99 <DECL.BAS>
100
     CLS
     PRINT "Control of the 9450 via GPIB and IBM PC"
110
115
     PRINT ""
120
     PRINT "Options : EX to exit
                                    LC local mode"
     PRINT "
                      ST store dataRC recall data"
125
     PRINT ""
130
     LINE INPUT "GPIB-address of oscilloscope (1...16)? : ", ADDR$
140
     DEV$ = "DEV" + ADDR$
145
     CALL IBFIND (DEV$, SCOPE%)
150
     IF SCOPE% < 0 THEN GOTO 830
155
     TMO\% = 10 'timeout = 300 msec (rather than default 10 sec)
160
165
     CALL IBTMO(SCOPE%, TMO%)
170
     LOOP\% = 1
200
205
     WHILE LOOP%
         LINE INPUT "Enter command (EX --> Exit) : ", CMD$
210
220
         IF CMD$ = "ex" OR CMD$ = "EX" THEN LOOP% = 0 : GOTO 310
         IF CMD$ = "st" OR CMD$ = "ST" THEN GOSUB 600 : GOTO 300
230
240
         IF CMD$ = "rc" OR CMD$ = "RC" THEN GOSUB 700 : GOTO 300
250
         IF CMD$ = "lc" OR CMD$ = "LC" THEN GOSUB 400 : GOTO 300
         IF CMD$ = "" THEN GOTO 300
260
270
         CALL IBWRT (SCOPE%, CMD$)
         IF IBSTA% < O THEN GOTO 840
275
280
         GOSUB 500
300
     WEND
310
     GOSUB 400
320
     END
400
405
     'SUBROUTINE LOCAL_MODE
410
420
     CALL IBLOC(SCOPE%)
425
     PRINT ""
430
     RETURN
500
505
     SUBROUTINE GET DATA
     'If there are no data to read, simply wait until timeout occurs
510
515
520
     CALL IBRD(SCOPE%, RD$)
525
     I = IBCNT% 'IBCNT% is the number of characters read
530
     FOR J = 1 TO I
535
         PRINT MID$(RD$, J, 1);
540
     NEXT J
     PRINT ""
545
550
     RETURN
600
```

```
605
      'SUBROUTINE STORE DATA
610
615
     RD1$=SPACE$(3)
620
     LINE INPUT "Specify trace (EA, EB, MC, MD, FE, FF, C1, C2): ", TRACE$
625
     LINE INPUT "Enter filename : ",FILE$
630
     CMD$="WFSU NP,0,SP,0,FP,0,SN,0; CHDR SHORT"
640
      CALL IBWRT (SCOPE%, CMD$)
     CMD$=TRACE$+":WF?"
645
650
      CALL IBWRT(SCOPE%, CMD$)
660
      CALL IBRD(SCOPE%, RD1$)
                                    'Discard first 3 chars of response
665
      CALL IBRDF (SCOPE%, FILE$)
670
      IF IBSTA% < 0 THEN GOTO 840
      PRINT ""
675
     RETURN
680
700
705
      'SUBROUTINE RECALL_DATA
710
715
     LINE INPUT "Specify target memory (MC, MD): ", MEM$
     LINE INPUT "Enter filename : ",FILE$
720
730
      CMD$=MEM$+":TRACE ON"
      CALL IBWRT (SCOPE%, CMD$)
735
740
     CALL IBWRTF (SCOPE%, FILE$)
      IF IBSTA% < 0 THEN GOTO 840
745
     PRINT ""
750
755
     RETURN
800
810
      'ERROR HANDLER
820
830
     PRINT "IBFIND ERROR"
835
840
     PRINT "GPIB ERROR -- IBERR: "; IBERR%; "IBSTA: "; HEX$(IBSTA%)
845
     END
```

EXAMPLE 3: GPIB PROGRAM FOR IBM PC (LOW-LEVEL FUNCTION CALLS)

The following example has the same function as example 2, but it is written with low level function calls.

The program assumes that the controller (board) and oscilloscope (device) are at addresses 0 and 4 respectively. The decimal listener and talker addresses of the controller and the device thus are:

	Listener address	Talker address		
controller	32 (ASCII <space>)</space>	64 (ASCII @)		
device	32+4=36 (ASCII \$)	64+4=68 (ASCII D).		

```
1-99 <DECL.BAS>
100
     CLS
     PRINT "Control of the 9450 (address 4) via GPIB and IBM PC"
110
115
     PRINT "": PRINT "Options : EX to exit
                                                     LC local mode"
120
     PRINT "
                        ST store data
                                           RC recall data": PRINT""
125
     LOOP=1
     CMD1$ = "?_@$" 'Unlisten, Untalk, Board talker, Device listener
130
     CMD2$ = "?_ D" 'Unlisten, Untalk, Board listener, Device talker
135
     BDNAME$= "GPIBO": CALL IBFIND(BDNAME$, BRDO%)
140
     IF BRDO% < 0 THEN GOTO 420
145
150
     CALL IBSIC(BRDO%): IF IBSTA% < 0 THEN GOTO 425
     WHILE LOOP
155
160
         LINE INPUT "Enter command (EX --> Exit) : ", CMD$
         V% = 1: CALL IBSRE (BRDO%, V%)
165
170
         IF CMD$ = "ex" OR CMD$ = "EX" THEN LOOP = FALSE: GOTO 205
175
         IF CMD$ = "st" OR CMD$ = "ST" THEN GOSUB 285: GOTO 200
         IF CMD$ = "rc" OR CMD$ = "RC" THEN GOSUB 365: GOTO 200
180
         IF CMD$ = "lc" OR CMD$ = "LC" THEN GOSUB 240: GOTO 200
185
190
         IF CMD$ = "" THEN GOTO 200
         CALL IBCMD(BRDO%, CMD1$): CALL IBWRT(BRDO%, CMD$): GOSUB 270
195
200
     CALL IBSIC(BRDO%): V%=0: CALL IBSRE(BRDO%, V%)
205
210
     CALL IBSIC(BRDO%)
215
     END
220
230
      'LOCAL MODE
235
240
     V% = 0: CALL IBSRE(BRDO%, V%): PRINT ""
245
     RETURN
250
      'SUBROUTINE GET_DATA
260
265
270
     CALL IBCMD(BRD0%, CMD2$): CALL IBRD(BRD0%, RD$): I=IBCNT%
     FOR J=1 TO I: PRINT MID$(RD$, J, 1); NEXT J: PRINT ""
275
280
     RETURN
285
      'SUBROUTINE STORE_DATA
290
295
300
     RD1$=SPACE$(3)
     LINE INPUT "Specify trace (EA, EB, MC, MD, FE, FF, C1, C2): ", TRACE$
305
310
     LINE INPUT "Enter filename : ",FILE$
315
     CALL IBCMD (BRDO%, CMD1$)
320
     CMD$="WFSU NP,O,SP,O,FP,O,SN,O;CHDR SHORT"
321
     CALL IBWRT (BRDO%, CMD$)
325
     CMD$=TRACE$+":WF?": CALL IBWRT(BRDO%, CMD$)
330
     CALL IBCMD(BRDO%, CMD2$): CALL IBRD(BRDO%, RD1$)
```

```
335
     CALL IBRDF(BRDO%, FILE$)
340
     IF IBSTA% < 0 THEN GOTO 430
345
     PRINT ""
350
     RETURN
355
360
     'SUBROUTINE RECALL_DATA
365
370
     LINE INPUT "Specify target memory (MC, MD): ", MEM$
     LINE INPUT "Enter filename : ",FILE$
375
380
     CALL IBCMD (BRDO%, CMD1$)
     CMD$=MEM$+":TRACE ON": CALL IBWRT(BRDO%,CMD$)
385
390
     CALL IBWRTF (BRDO%, FILE$)
395
     IF IBSTA% < 0 THEN GOTO 430
400
     PRINT ""
405
     RETURN
410
415
     'ERROR HANDLER
420
425
     PRINT "IBFIND ERROR": STOP
430
     PRINT "GPIB ERROR -- IBERR : "; IBERR%; "IBSTA : "; HEX$(IBSTA%)
435
     STOP
440
     END
```

APPENDIX B

THE WAVEFORM TEMPLATE

This is the response of the instrument to a command of the form TMPL?

```
TMPL. "
/00
                    LECROY_1_1: TEMPLATE
000000
                    8 66 109
; Explanation of the formats of waveforms and their descriptors on the
; LeCroy Digital Oscilloscopes,
      Software Release 33.1.1.2, 89/08/24.
; A descriptor and/or a waveform consists of one or several logical data blocks
; whose formats are explained below.
; Usually, complete waveforms are read: at the minimum they consist of
        the basic descriptor block WAVEDESC
        a data array block.
; Some more complex waveforms, e.g. envelope data or the results of a Fourier
; transform, may contain several data array blocks.
; When there are more blocks, they are in the following sequence:
        the basic descriptor block WAVEDESC
        the history text descriptor block USERTEXT (may or may not be present)
        the time array block (for RIS and sequence acquisitions only)
        data array block
        auxiliary or second data array block
; With the exception of the data and time arrays, every block starts with
; an 8-character name which identifies which kind of block it is.
; In the following explanation, every element of a block is described by a
; single line in the form
; <byte position> <variable name>: <variable type> ; <comment>
   where
    <byte position> = position in bytes (decimal offset) of the variable,
                      relative to the beginning of the block.
    <variable name> = name of the variable.
    <variable type> = string
                                    up to 16-character name
                                      terminated with a null byte
                        bvte
                                     8-bit signed data value
                        word
                                    16-bit signed data value
                                    32-bit signed data value
                        long
                                    32-bit IEEE floating point value
                        float
```

```
with the format shown below
                           3 ... 2
                                      2 ...
                                                 bit.
                           0
                                      2
                       1
                                  3
                                             0
                                                 position
                                      fraction
                       s
                           exponent
                       where
                       s = sign of the fraction
                       exponent = 8 bit exponent e
                       fraction = 23 bit fraction f
                       and the final value is
                       (-1)**s * 2**(e-127) * 1.f
         double
                       64-bit IEEE floating point value
                       with the format shown below
                           6 ... 5 5 ...
                                  2
                                      1
                                                 positon
                           exponent
                                      fraction
                       where
                       s = sign of the fraction
                       exponent = 11 bit exponent e
                       fraction = 52 bit fraction f
                       and the final value is
                       (-1)**s * 2**(e-1023) * 1.f
           enum
                       enumerated value in the range O to N
                       represented as a 16-bit data value.
                       The list of values follows immediately.
                       The integer is preceded by an _ .
     time_stamp
                       double precision floating point number,
                       for the number of seconds and some bytes
                       for minutes, hours, days, months and year.
                       double seconds
                                           (0.00 to 59.999999)
                       byte
                               minutes
                                           (0 to 59)
                       byte
                               hours
                                           (0 to 23)
                               days
                       byte
                                           (1 to 31)
                       byte
                               months
                                           (1 to 12)
                       word
                               year
                                            (0 to 16000)
                       word
                               unused
                       There are 16 bytes in a time field.
           data
                       byte, word or float, depending on the
                       read-out mode reflected by the WAVEDESC
                       variable COMM_TYPE, modifiable via the
                       remote command COMM_FORMAT.
           text
                       arbitrary length text string
                       (maximum 400)
unit_definition
                       a unit definition consists of a 48 character
                       ASCII string terminated with a null byte
                       for the unit name.
```

```
WAVEDESC: BLOCK
; Explanation of the wave descriptor block WAVEDESC;
< 0>
               DESCRIPTOR_NAME: string ; the first 8 chars are always WAVEDESC
               TEMPLATE_NAME: string
< 16>
< 32>
               COMM_TYPE: enum
                                        ; chosen by remote command COMM_FORMAT
               _0
                       byte
               _1
                       word
               endenum
< 34>
               COMM ORDER: enum
               _0
                      HIFIRST
                      LOFIRST
               _1
               endenum
; The following variables of this basic wave descriptor block specify
; the block lengths of all blocks of which the entire waveform (as it is
; currently being read) is composed. If a block length is zero, this
; block is (currently) not present.
;BLOCKS :
< 36>
               WAVE DESCRIPTOR: long
                                         ; length in bytes of block WAVEDESC
< 40>
               USER_TEXT: long
                                         ; length in bytes of block USERTEXT
< 44>
               RES_DESC1: long
; ARRAYS :
                                         ; length in bytes of TRIGTIME array
< 48>
               TRIGTIME_ARRAY: long
               RIS_TIME_ARRAY: long
                                         ; length in bytes of RIS_TIME array
< 52>
               RES_ARRAY1: long
                                         ; an expansion entry is reserved
< 56>
               WAVE_ARRAY_1: long
                                         ; length in bytes of 1st simple
< 60>
                                         ; data array. In transmitted waveform,
                                         ; represent the number of transmitted
                                         ; bytes in accordance with the NP
```

```
; parameter of the WFSU remote command
                                         ; and the used format (see COMM_TYPE).
               WAVE_ARRAY_2: long
< 64>
                                         ; length in bytes of 2nd simple
                                         ; data array
< 68>
               RES_ARRAY2: long
< 72>
               RES_ARRAY3: long
                                         ; 2 expansion entries are reserved
; The following variables identify the instrument
< 76>
               INSTRUMENT_NAME: string
< 92>
               INSTRUMENT_NUMBER: long
< 96>
               TRACE_LABEL: string
                                         ; identifies the waveform.
<112>
               RESERVED1: word
               RESERVED2: word
<114>
                                         ; 2 expansion entries
; The following variables describe the waveform and the time at
; which the waveform was generated.
<116>
               WAVE_ARRAY_COUNT: long
                                        ; number of data points in the data
                                         ; array. If there are two data
                                         ; arrays (FFT or Envelope), this number
                                         ; applies to each array separately.
<120>
               PNTS_PER_SCREEN: long
                                         ; nominal number of data points
                                         ; on the screen
               FIRST_VALID_PNT: long
<124>
                                         ; count of number of points to skip
                                         ; before first good point
                                         ; FIRST_VALID_POINT = 0
                                         ; for normal waveforms.
<128>
               LAST_VALID_PNT: long
                                         ; index of last good data point
                                         ; in record before padding(blanking)
                                         ; was started.
                                         ; LAST_VALID_POINT = WAVE_ARRAY_COUNT-1
                                         ; except for aborted sequence
                                         ; and rollmode acquisitions
              FIRST POINT: long
<132>
                                         ; for input and output, indicates
                                         ; the offset relative to the
                                         ; beginning of the trace buffer.
```

		; Value is the same as the FP parameter
		; of the WFSU remote command.
;		
<136>	SPARSING_FACTOR: long	; for input and output, indicates
		; the sparsing into the transmitted
		; data block.
		; Value is the same as the SP parameter
		•
		; of the WFSU remote command.
;		
<140>	SEGMENT_INDEX: long	; for input and output, indicates the
		; index of the transmitted segment.
		; Value is the same as the SN parameter
		; of the WFSU remote command.
;		
<144>	SUBARRAY_COUNT: long	; actual number of subblocks within the
12.00		; data array. (to be used in sequences)
		, data array. (to be about in bequences)
, , , , , , , , , , , , , , , , , , , ,	GWEEDG DED 400. long	. for BIC on Cognopos Averages
<148>	SWEEPS_PER_ACQ: long	; for RIS or Sequence, Averages,
		; it is the nominal number
;		
<152>	NUMBER_REJECTED: long	; number of sweeps rejected
		; while doing averaging
;		
<156>	VERTICAL_GAIN: float	
;		
<160>	VERTICAL_OFFSET: float	; to get floating values from raw data :
	_	; VERTICAL_GAIN * data - VERTICAL_OFFSET
;		
, <164>	MAX VALUE: float	; maximum allowed value. It corresponds
11017		; to the upper edge of the grid.
		, to the apper cage of the gria.
,100	MIN VALUE, floor	, minimum allowed walve. It commemorate
<168>	MIN_VALUE: float	; minimum allowed value. It corresponds
		; to the lower edge of the grid.
;		
<172>	NOMINAL_BITS: word	; a measure of the intrinsic precision
		; of the observation: ADC data is 8 bit
		; averaged data is 10-12 bit, etc.
;		
<174>	RESERVED7: word	; expansion entry
:		· · · · · · · · · · · · · · · · · · ·
, <176>	HORIZ INTERVAL: float	; sampling interval for time domain
		: waveforms
•		, "4" 0101 110
;		
-1.00	HODER OFFICERS, double	. twiggen affact for the fingt amount of
<180>	HORIZ_OFFSET: double	; trigger offset for the first sweep of
<180>	HORIZ_OFFSET: double	; trigger offset for the first sweep of ; the trigger, seconds between the ; trigger and the first data point

```
<188>
               PIXEL_OFFSET: double
                                          ; needed to know how to display the
                                          ; waveform
               {\tt VERTUNIT:\ unit\_definition\quad;\ units\ of\ the\ vertical\ axis}
<196>
<244>
               HORUNIT: unit_definition
                                            ; units of the horizontal axis
<292>
               RESERVED3: word
<294>
               RESERVED4: word
                                          ; 2 expansion entries
<296>
               TRIGGER_TIME: time_stamp ; time of the trigger
               ACQ_DURATION: float
<312>
                                          ; duration of the acquisition (in sec)
                                          ; in multi-trigger waveforms.
                                          ; (e.g. sequence, RIS, or averaging)
<316>
               RECORD_TYPE: enum
               _0
                        single_sweep
               _1
                        interleaved
               _2
_3
_4
_5
                        histogram
                        trend
                        filter coefficient
                        complex_frequency_domain
               _6
                        extrema_-_envelope_display
               _7
                        sequence
               endenum
<318>
               PROCESSING DONE: enum
               _0
                         no_processing
               _1
                         fir_filter
               _2
_3
_4
_5
_6
_7
                         interpolated_waveform
                         sparsed_waveform
                         autoscaled_waveform
                         no_result_waveform
                         rolling waveform
                         cumulative_waveform
               endenum
               RESERVED5: word
<320>
               RESERVED6: word
<322>
                                          ; 2 expansion entries
; The following variables describe the basic acquisition
; conditions used when the waveform was acquired
```

<324> TIMEBASE: enum _0 1_ps/div _1 2_ps/div _2 5_ps/div _3 10_ps/div 20_ps/div 50_ps/div _6 _7 100_ps/div 200_ps/div 500_ps/div _9 1_ns/div _10 2_ns/div _11 5_ns/div _12 10_ns/div _13 20_ns/div _14 50_ns/div _15 100_ns/div _16 200_ns/div _17 500_ns/div _18 1_us/div _19 2_us/div _20 5_us/div _21 10_us/div _22 20_us/div _23 50_us/div 100_us/div _24 _25 200_us/div _26 500_us/div _27 1_ms/div 2_ms/div _28 _29 5_ms/div _30 10_ms/div _31 20_ms/div _32 50_ms/div _33 100_ms/div _34 200_ms/div _35 500_ms/div _36 1_s/div 2_s/div _37 _38 5_s/div _39 10_s/div _40 20_s/div _41 50_s/div _42 100_s/div

_43

_44

200_s/div

500_s/div

```
_45
                     1_ks/div
               _46
                     2_ks/div
               _47 5_ks/div
               _100 EXTERNAL
               endenum
<326>
               VERT_COUPLING: enum
               _0
                        DC_50_Ohms
               _1
                        ground
               _2
                        DC_1MOhm
               _3
                        ground
               _4
                        AC,_1MOhm
               endenum
               PROBE_ATT: float
<328>
               FIXED_VERT_GAIN: enum
<332>
               _0 1_uV/div
               _3 10_uV/div
_4 20_uV/div
_5 50_uV/div
_6 100_uV/div
_7 200_uV/div
               _8
                    500_uV/div
               _9
                    1_mV/div
               _10 2_mV/div
               _11 5_mV/div
               _12 10_mV/div
               _13 20_mV/div
               _14 50_mV/div
               _15 100_mV/div
               _16 200_mV/div
               _17 500_mV/div
               _18 1_V/div
               _19 2_V/div
               _20 5_V/div
               _21 10_V/div
               _22 20_V/div
               _23 50_V/div
               _24 100_V/div
               _25 200_V/div
               _26 500_V/div
               _27 1_kV/div
               endenum
```

```
BANDWIDTH_LIMIT: enum
<334>
                       off
                       on,_80_MHz
               _1
endenum
               VERTICAL_VERNIER: float
<336>
              ACQ_VERT_OFFSET: float
<340>
               WAVE_SOURCE: enum
<344>
                       CHANNEL_1
               _0
                       CHANNEL_2
               _1
               _2
                       CHANNEL_3
               _3
                       CHANNEL_4
               _9
                       UNKNOWN
               endenum
                 ENDBLOCK
/00
;
USERTEXT: BLOCK
; Explanation of the descriptor block \mbox{ USERTEXT } at most 400 bytes long.
<
               DESCRIPTOR_NAME: string ; the first 8 chars are always USERTEXT
< 16>
               TEXT: text
                                         ; this is simply a list of ASCII
                                         ; characters
                 ENDBLOCK
/00
SIMPLE: ARRAY
; Explanation of the simple data array
; The data item is repeated for each acquired or computed data point
; of the first data array of any waveform.
               MEASUREMENT: data
                                         ; the actual format of a data is
< 0>
                                         ; given in the WAVEDESC descriptor
                                         ; by the COMM_TYPE variable.
```

```
/00
               ENDARRAY
;
DATA_ARRAY_1: ARRAY
; Explanation of the data_array_1 array.
; The data item is repeated for each acquired or computed data point
; of the first data array of any waveform.
; It is identical to SIMPLE above.
             MEASUREMENT: data
                                   ; the actual format of a data is
                                   ; given in the WAVEDESC descriptor
                                   ; by the COMM_TYPE variable.
/00
               ENDARRAY
DATA_ARRAY_2: ARRAY
; Explanation of the data_array_2 array.
; The data item is repeated for each acquired or computed data point
; of the second data array of any dual waveform
; e.g. the imaginary part of a FFT.
             MEASUREMENT: data
< 0>
                                  ; the actual format of a data is
                                   ; given in the WAVEDESC descriptor
                                   ; by the COMM_TYPE variable.
/00
               ENDARRAY
DUAL: ARRAY
; Explanation of the dual array.
; This data block is repeated for each pair of computed data points
; composing respectively the first and second data array of a waveform,
; e.g the real and imaginary parts of an FFT.
< 0>
             MEASUREMENT_1: data
                                  ; data in the first data array.
```

```
; the actual format of a data is
                                     ; given in the WAVEDESC descriptor
                                     ; by the COMM_TYPE variable.
              MEASUREMENT_2: data
                                     ; data in the second data array
< 0>
                                     ; the byte offset depends on
                                     ; the actual format of the data which
                                     ; is given in the WAVEDESC descriptor
                                     ; by the COMM_TYPE variable.
/00
               ENDARRAY
TRIGTIME: ARRAY
; Explanation of the trigger time array
; This data block is repeated for each segment which makes up the acquired
; sequence record.
< 0>
              TRIGGER_TIME: double
                                     ; for sequence acquisitions,
                                     ; time in seconds from first
                                     ; trigger to this one
              TRIGGER_OFFSET: double
                                    ; the trigger offset is in seconds
 8>
                                     ; from trigger to zero'th data point
;
                ENDARRAY
/00
RISTIME: ARRAY
; Explanation of the random-interleaved-sampling (RIS) time array
; This data block is repeated for each sweep which makes up the RIS record
              RIS_OFFSET: double
                                     ; seconds from trigger to zero'th
< 0>
                                     ; point of segment
/00
                ENDARRAY
;
000000
                   ENDTEMPLATE
```

		appropriate for the state of th
		easepalate and the control of the co
		Adapta addy distribution — man — filter metro-
		Provide Application and the control of the control
		in die voorbeerd gewone van de deer de verden van de verden va
		Country park from collaboration on an Alberto
		nadrala minery vido VIII ROANI (NAMA)
		manal immanada meri risanuari.
		form the fact that the color
		No. — No promote the services
		edalah panta terapa kingan
		of a substitution of the same of the same
		Autoritoristation at 4 Magazine
		dinostrones. *
		gran, diproductions
		1

INDEX

This index does not contain entries for each of the remote commands. They can be found in alphabetical order in section 5. Furthermore, the index does not contain references to the command descriptions in section 5.

DDR - Device Dependent error status Regis-A ter, 176 Assistance, 1 Descriptor Block, 159, 163 B Values, 161, 163 Diagnostics Help Messages, 4 BASIC(A), 15-22, 161, 180 DUAL, 160, 161 Binary Blocks, 163 \mathbf{E} \mathbf{C} Error Messages, 4 CMR - CoMmand error Register, 171, 173, 174, 176 ESE - Standard Event Status Enable register, 20, 171, 173, 175 Command Execution, 37 ESR - Standard Event Status Register, 20, Command Notation, 37-38 171-174 Command Summary, 35-36 EXR - EXecution error Register, 171, 176 Commands and Queries, 4, 6-9 Continuous Polling, 21 G Controller Timeout, 4, 13, 19, 22, 180 Customer Service, 1-2 GPIB, 11 Address switches, 3, 12, 25 ATN - ATteNtion, 12 D Data lines, 12 Data DCL - Device CLear, 14 EOI - End Or Identify, 5, 13 Arrays, 159, 160 ASCII forms, 7-9 GET - Group Execute Trigger, 14, 19 GTL - Go To Local, 14, 18 Blocks, 159 Handshake lines, 12 Formatting, 161, 163, 168 HEX mode, 29, 33, 162, 168 Hard copies, 25-27 Horizontal position, 165-167 Hardware Configuration, 15 Interpretation, 162-165 IEEE 488.1, 3, 13-15, 24 IEEE 488.2, 3, 13, 171, 174 Sparsing, 168

IFC - InterFace Clear, 12, 15 Interface capabilities, 11

Time of, 165-167

Values, 161, 163-166

Interface management lines, 12-13 IBRSP, 22 Listener address, 24 IBTMO, 19 LLO - Local LOckout, 14 IBTRG, 19 MLA - Listen address, 12, 24, 27 IBWAIT, 19, 22 MTA - Talker address, 12, 24, 27 Polling, 21-25 IBWRT, 16 Programs for GPIB, 15-18, 21-26, IBWRTF, 18 179 - 182IBWRTI, 18-19 REN - Remote ENable, 13, 14 IEEE Standards. See GPIB RQS - ReQuest for Service, 22 SDC - Selected Device Clear, 14, 18 INE - INternal state change Enable register, Signals, 12-13 20, 22, 23, 25, 171, 173, 176 Software Configuration, 15 INR - INternal state change Register, 20, SRE - Service Request Enable register, 21, 22, 23, 25, 171, 173, 175 19, 22 INSPECT? Queries, 160-162 SRQ - Service ReQuest, 13, 19-20 Interface Messages, 11 Talker address, 24 Transfers, 15 IST Polling, 24-25, 173, 175 UNL - Universal unlisten, 12, 24-25, 27 UNT - Universal untalk, 12, 24-25, 27 L

H

Hard Copies. See GPIB Header, 6-7 Header Path, 7 Help Messages, 4

I

IBCLR, 18
IBCMD, 23
IBFIND, 16
IBLOC, 18
IBRD, 16
IBRDF, 18
IBRDI, 18—19
IBRPP, 24

Line Splitting. See RS-232-C Local State, 5 Logical Data Blocks, 159

\mathbf{M}

Maintenance, 1

P

PaRallel poll Enable register. See PRE
Parallel Polling, 23—24
Pin Assignments. See RS-232-C
Polling, 21—25
PRE - PaRallel poll Enable register, 23, 24, 173, 175
Program Messages, 3—4, 5—6

R Status Register Reporting, 171 STB - STatus Byte register, 20-25, 32, RAN - Return Authorization Number, 2 171-174 Remote State, 5 Suffix Multipliers, 8-9 Response Message Form, 9-10 Return Procedure, 2 T RISTIME, 160, 167 Template, 159, 160, 163, 164, 165, RS-232-C, 29 185 - 195Configuration, 30 Terminators, 5, 9, 31, 164 Echoing, 30 Editing, 31 Thumbwheel Switch. See GPIB Address Handshake control, 30-31 Switches Immediate commands, 30 Transfers. See GPIB Line splitting, 32-33 Trigger Time, 160 Message terminators, 31 TRIGTIME, 159, 166 Pin assignments, 29-30 Simulating GPIB commands, 33 $-\mathbf{U}$ SRQ - Service request, 32 URR - User Request status Register, 20, S 176 USERTEXT, 159 Serial Polling, 22 Service Procedure, 2 W Service Requests, 171-173 SIMPLE, 160 Warning Messages, 4 SRE - Service Request Enable register, 19, Warranty, 1 171, 173, 175 WAVEDESC. See Descriptor SRQ - Service ReQuest, 19-21, 32, WAVEFORM 173-174 Command, 167 Standard Event Status Enable Register. See Query, 162-167, 168 Transfer Optimization, 168-169 Waveform Template, 185-195 Standard Event Status Register. See ESR

			asson and any
			Nagapa Abanda kecama
			de de la receive
			estatistica del proprieta del de
			epotential photo en _{cultimorphis} de
			La constitution of the con
			e colin e e con e e e colin e e colin e e colin e e e colin e e e colin e e e e e e e e e e e e e e e e e e e
			graph-besser or a .
		- %	*Parameters control and a cont
			A STATE OF THE PARTY OF THE PAR
			of allowed and a second a second and a second a second and a second a
			ene esta sue subsenione
			od in visit was the case (1991 and
			Appel de November de maleira en vert en
			set and other or my set from
			Procedure Control
			*Amplicition***********************************
			* whaterpark
			*North Management of the State
			- Appendix such
			Land 1
			Complement
			94

ADDRESSES

US SALES OFFICES

800-5-LeCroy (automatically connects you to your local sales office)

WORLDWIDE

Argentina: Search SA, (01) 394-5882 Australia: Scientific Devices Pty.Ltd, (03) 579-3622

Austria: Dewetron Elek. Messgeräte GmbH,

(0316) 391804

Benelux: LeCroy B.V., 31-4902-89285 Brazil: A. Santos, (021) 233 5590 Canada: Rayonics, W. Ontario:

(416) 736–1600

Rayonics, E. Ontario/Manitoba:

(613) 521-8251 Rayonics, Quebec: (514) 335-0105 Rayonics, W. Canada: (604) 293-1854

Denmark: Lutronic, (42) 459764 Finland: Labtronic OY, (90) 847144 France: LeCroy Sarl (1) 69073897

Germany: LeCroy GmbH, (06221) 49162 (North) (0405) 42713

Greece: Hellenic S/R Ltd., (01) 721 1140 India: Electronic Ent., (022) 4137096

Israel: Ammo, (03) 453157

Italy: LeCroy S.r.l.,Roma (06) 302-9646 Milano (02) 2940-5634 (02) 204 7082

Japan: Toyo Corp., (03) 279 0771 Korea: Samduk Science & Ind., Ltd.:

(02) 468 04914

Mexico: Nucleoelectronica SA: (905) 593 6043

New Zealand: E.C. Gough Ltd., (03) 798-740

Norway: Avantec A/S, (02) 630520

Pakistan: Electronuclear Corp., (021) 418087

Portugal: M.T. Brandao, Lta., (02) 691116

Singapore: Singapore Electronics and Eng. Ltd., (065) 481 8888

Spain: Anadig Ingenieros SA, (01) 433 2412

Sweden: MSS AB, (0764) 68100

Switzerland: LeCroy S.A. (022) 719 21 11

Taiwan: Topward El. Inst., Ltd., (02) 601 8801

Thailand: Measuretronix Ltd., (02) 374 2516

United Kingdom: LeCroy Ltd., (0235) 33 114

LeCROY CORPORATE HEADQUARTERS

700 Chestnut Ridge Road Chestnut Ridge, NY 10977-6499 Telephone: (914) 578 6097 TWX:(710) 577-2832 Fax: (914) 425-8967

LeCROY EUROPEAN HEADQUARTERS

2 chemin Pré-de-la-Fontaine P.O. Box 341

1217 Meyrin 1/Geneva, Switzerland Tel.: (022) 719 21 11 Telex: 419 058

Fax: (022) 782 39 15